

INVITE-ONLY SCRIPT



Updated Jul 26

Intelligent Balance Probability Map+ [Herman]


Chart



Add to favorites

Micro E-mini Nasdaq-100 Index Futures · 1 · CME

Intelligent Balance Probability Map+ [Herman]



Use on chart

17



477

Apr 15

Intelligent Balance Probability Map [Herman]

Overview

The **Intelligent Balance Probability Map** is a premium session-analysis tool built for traders — particularly scalpers — who base their trading decisions on the behaviour of a defined opening range window.

The indicator automatically identifies your chosen Initial Balance (IB) takes into consideration market conditions in real time, and calculates a directional probability for where price is most likely to travel first after the chosen custom session closes.

The result is a clean, visual map of probable targets above and below the IB — backed by quantitative context and updated on every bar.

What Is the Initial Balance?

The Initial Balance is the price range established during a defined opening window of a trading session. It represents the market's early price discovery phase and is widely used by professional traders as a reference for the rest of

Invite-only script ?

Only users approved by the author can access this script. You'll need to request and get permission to use it. This is typically granted after payment. For more details, follow the author's instructions below or contact [helmans13](#) directly.

Note that this private, invite-only script has not been reviewed by script moderators, and its compliance with [House Rules](#) is undetermined. TradingView does NOT recommend paying for or using a script unless you fully trust its author and understand how it works. You may also find free, open-source alternatives in our [community scripts](#).

Author's instructions

Access for Premium Members only.

Official Website:

<http://www.HermanTrading.Pro>

Join the Community:

<https://discord.gg/7tWKTTFnJk>

Warning: please read [our guide](#) for

phase and is widely used by professional traders as a reference for the rest of the session.

This indicator lets you define any session window you want — standard NY open (09:30–10:30), London open, overnight sessions, or any custom range.

How the Probability Engine Works

At the close of your IB window, the indicator runs a multi-factor scoring engine across **8 independent market conditions**. Each condition votes for or against a bullish or bearish extension. The scores are weighted, normalised, and converted into a directional probability expressed as a percentage.

The engine evaluates:

1. **Price location relative to VWAP** — where price sits against the volume-weighted average price of the session
2. **HTF EMA bias** — the trend direction on a higher timeframe moving average (user-configurable: 15m / 1H / 4H, EMA 50 or 200)
3. **Market trend state** — whether recent price structure favours buyers or sellers over a configurable lookback
4. **Order flow momentum** — the cumulative direction of buying vs selling pressure within the current session, reset daily
5. **Price imbalance pressure** — the presence and weight of unfilled price inefficiencies above or below current price
6. **HTF structural level proximity** — whether the 0.5x IB extension target aligns with a significant higher timeframe reference level
7. **Opening bias** — whether the session opened above or below the previous session's close, creating directional pressure
8. **Liquidity event context** — whether a significant stop-hunt or liquidity sweep occurred within the IB window, which shifts directional bias

What Gets Drawn on the Chart

IB Box

A box is drawn over your defined session window, automatically expanding as price moves. The midpoint of the IB is marked with a dashed line.

When Heatmap is ON: the box fills with a colour gradient — green tones for bullish bias, red tones for bearish. The stronger the probability, the more saturated the colour.

When Heatmap is OFF: the box is displayed in neutral light grey.

Extension Targets

Two dotted lines extend beyond the IB box:

- The **primary target** — positioned above/below the IB range beyond the IB high (bull) or IB low (bear). This is where the indicator projects price is most

... ..

invite-only scripts before requesting access.



helmans13

Follow

Also on:

Disclaimer

The information and publications are not meant to be, and do not constitute, financial, investment, trading, or other types of advice or recommendations supplied or endorsed by TradingView. Read more in the [Terms of Use](#).

likely to travel first.

- The **counter target** — positioned above/below the IB range on the opposite side.

Each line is labelled with its probability percentage.

Lines with a **⚡** prefix indicate an Edge condition (above your configured threshold).

Below 60%: both lines and labels are displayed in grey — the indicator flags this as a low-confidence, no-edge setup. The setup is still shown for reference but visually de-emphasised.

Volatility Zones

Thin shaded bands around each extension target indicate a price reaction zone, scaled proportionally to the IB range.

Hit Detection

When price reaches either target after the IB closes:

- **✓** is plotted if the primary target is hit first (a win for the projected direction)
- **✗** is plotted if the counter target is hit first (the projection was wrong)

These are used to build the running statistics in the dashboard table.

IB Context Label

A label is pinned above every IB box showing three pieces of information:

...

IB: 76pt | Avg: 112pt | ACCUMULATION **◆**

...

- **IB range in points** — the actual size of today's IB window
 - **Avg** — the rolling average IB range of the last x sessions *of this specific window*. This is the key reference point for classification.
- A London 1:00–2:00 AM IB is compared to other London IBs, not to the full NY daily range.
- **Classification:**
 - **ACCUMULATION **◆**** — today's IB is more than 30% smaller than its own session average. Price is compressed — expect a sharper, more decisive extension move. The IB box border turns **orange**.
 - **NORMAL **◆**** — today's IB is within a typical range for this session window.
 - **EXPANDED **△**** — today's IB is more than 40% larger than its session average. Extensions are less reliable as the range is already stretched.

> **Important:** The classification is meaningful only after the indicator has recorded at least 3 sessions of the same IB window. During the initial warm-up period the label shows **"BUILDING HISTORY..."**. Full reliability is reached after approximately 10–15 sessions.

Confluence Badge

Below the IB box, a detailed breakdown badge is displayed showing how each of the 8 factors voted:

...

▲ BULL 77%

✓ VWAP ✓ EMA

✓ Trend ✓ Flow

✓ Imbalance ✓ Liq.

✓ HTF Lvl ✓ Open

Confluence: 8/8

...

Each factor shows ✓ (aligned with the projected direction) or ✕ (misaligned). The Confluence score shows how many factors agreed with the winning side.

****How to read the badge:****

- 7–8/8 with high % → very high conviction setup
- 5–6/8 → moderate conviction, still tradeable
- 4/8 or below → conflicting market conditions, treat with caution

Statistics Dashboard

A persistent table (configurable position and size) tracks the indicator's historical performance on your chart:

| Field | Description |

|---|---|

| ****General Hit Rate**** | % of all setups where the primary target was reached first |

| ****Setups [W / L]**** | Total tracked setups, wins and losses |

| ****Edge Mode ≥X%**** | Filtered stats for only high-probability setups above your threshold |

| ****Edge Hit Rate**** | Win rate when only Edge setups are counted |

| ****Edge [W / L]**** | Edge setup counts |

| ****IB Time**** | Your currently configured session window |

| ****Last Bias**** | Direction and probability of the most recent session |

| ****Confluence**** | Factor score of the most recent session |

| ****Trend Filter**** | Active HTF EMA settings |

> Statistics accumulate from bars visible on your chart. For meaningful data, ensure you have sufficient history loaded (right-click chart → "Add more bars").

Settings Reference

IB Session

| Setting | Description |

|---|---|

| IB Session (NY Time) | Define your session window in New York time. Example: 0930-1030 for standard NY open, 0100-0200 for London. |

| IB Box Background | Box fill colour (active when Heatmap is OFF) |

| IB Border Color | Box border colour (overridden by Edge/Accumulation logic) |

| Highlight Edge Sessions | Thickens the border on high-probability setups |

| Edge Border Width | Border thickness for Edge sessions (1–10) |

Premium Quant Matrix

| Setting | Description |

|---|---|

| Show VWAP | Displays session VWAP on the chart |

| Show HTF EMA | Displays higher timeframe EMA |

| TF | Higher timeframe for EMA: 15m, 1H, or 4H |

| EMA Length | 50 or 200 |

| Use HTF Level Confluence | Enables Factor 6 — checks if extension target aligns with a key HTF structural level |

| Open Bias Filter | Enables Factor 7 — considers opening gap direction |

| Liquidity Event Detection | Enables Factor 8 — detects stop hunts / liquidity sweeps within the IB |

| Event Lookback | Lookback window for sweep detection (bars) |

| Signal Decay (bars) | How long a sweep signal stays active after detection. For a 60-minute IB on 1m chart = 60 bars minimum recommended. |

| Trend Lookback | Lookback bars for market structure assessment (Factor 3) |

| Imbalance Weight | Multiplier for Factor 5 (price imbalance). Higher = imbalance has more influence. Options: 1, 2, 3. |

Extensions & Probabilities

| Setting | Description |

|---|---|

| Bull Ext / Bear Ext | Colours for bull and bear extension lines and zones |

| Width | Extension line thickness |

| Shorten | Shorter extension lines (80 bars vs 200) |

| Show Hit Icons | Displays / when targets are hit |

| Bull/Bear Label | Probability label text colours |

| Size | Label text size |

Premium Visuals & Alerts

| Setting | Description |

|---|---|

| Probability Heatmap | Fills IB box with a directional colour gradient |

| Volatility Zones | Shaded bands around extension targets |

| Confluence Badge | Shows the factor breakdown below the IB box |

| IB/ATR Context Label | Shows IB range, session average, and classification above the box |

| Strategy Alerts | Fires alerts on Edge detection and target hits |

Statistics Table

| Setting | Description |

|---|---|

| Show Table | Toggle the dashboard |

| Theme | Dark or Light |
 | Edge Threshold % | Minimum probability to qualify as an Edge setup (51–95%)
 |
 | Size | Table text size |
 | Position | Table corner position |

History

Setting	Description
Days to Show	How many past IB sessions are drawn (1–50)

Alerts

Two alert conditions are available (enable via **Strategy Alerts** input):

1. ****Edge Detected**** — fires at IB close when probability exceeds your Edge Threshold. Message includes direction, probability %, and confluence score.
2. ****Target Hit**** — fires when price reaches a primary extension target. Message includes win count.

To set up: add the indicator, enable Strategy Alerts in settings, then use TradingView's **Create Alert** → select this indicator → choose "Any alert() function call".

Important Notes

- ****Timeframe:**** The indicator is designed for ****1-minute and 5-minute charts****. On higher timeframes the IB session may collapse to very few bars and lose accuracy.
- ****Instrument:**** Optimised for NQ and ES futures. Compatible with any instrument but default settings (IB window, EMA length) are calibrated for index futures.
- ****Repainting:**** The indicator does ****not repaint****. All drawings and probabilities are calculated and fixed at the close of the IB session bar. No values change after that bar closes.
- ****Statistics cold start:**** Statistics begin accumulating from the first IB session visible on your loaded chart. The more history you load, the more meaningful the hit rate numbers become.
- ****Classification warm-up:**** ACCUMULATION / NORMAL / EXPANDED labels require a minimum of 3 completed sessions of the same IB window. Until then, the label shows ****"BUILDING HISTORY..."****

Frequently Asked Questions

****Q: Why does it show "BUILDING HISTORY..." on the context label?****

The indicator needs at least 3 completed sessions of your specific IB window to

calculate a meaningful average range. This typically clears after the first 3 trading days. Do not change the session window frequently as it resets the history.

****Q: My hit rate shows 0% — what's wrong?****

Statistics are calculated only from sessions visible on your chart. Make sure you have sufficient price history loaded. Right-click the chart → "Add more bars to the left" to extend history.

****Q: What does ⚡ before the percentage mean?****

It means this session qualifies as an Edge setup — the probability exceeded your configured Edge Threshold %. These are the highest-conviction signals the indicator produces.

****Q: The classification was ACCUMULATION but price barely moved. Why?****

ACCUMULATION means the IB range was compressed relative to its own historical average — it does not guarantee a large extension. It signals potential, not certainty. Always combine with the probability score and confluence count.

****Q: Can I use this on stocks or crypto?****

Yes. The core logic works on any instrument. However, the default settings (signal decay, lookback values) are tuned for liquid index futures. You may need to adjust Imbalance Weight and Event Lookback for lower-liquidity instruments.

****Q: What is the difference between Edge Hit Rate and General Hit Rate?****

General Hit Rate counts every setup regardless of probability. Edge Hit Rate counts only setups where the probability exceeded your Edge Threshold (default 70%). Edge setups are expected to have a higher win rate — if they don't after a reasonable sample (20+ setups), consider adjusting your threshold.

****Q: Can I use two instances for different sessions (London + NY)?****

Yes. Add the indicator twice, set different IB Session windows for each. Each instance maintains its own independent history and statistics.

Intelligent Balance Probability Map is an original indicator by Herman Trading. All rights reserved. Unauthorised reproduction or distribution of this indicator is prohibited.

May 4

Release Notes

Added filters info to the table & Probability zone customisation.

May 19

Release Notes

Updated:

History - Days to show bug fix

Display - Added more display lines options.

Jul 26

Release Notes

Default settings change:

EMA 15/50
Trend Lookback 10

(Same at the one I am using)

MADE BY HUMANS   English Select market data provided by ICE Data Services. Select reference data provided by FactSet. Copyright © 2026 FactSet Research Systems Inc. Copyright © 2026, American Bankers Association. CUSIP Database provided by FactSet Research Systems Inc. All rights reserved. SEC filings and other documents provided by Quartr. © 2026 TradingView, Inc.	MORE THAN A PRODUCT Supercharts SCREENERS Stocks ETFs Bonds Crypto coins CEX pairs DEX pairs Pine HEATMAPS Stocks ETFs Crypto coins CALENDARS Economic Earnings Dividends IPOs MORE PRODUCTS Portfolios Yield Curves Options Macro Maps Pine Script® APPS Mobile Desktop	TOOLS & SUBSCRIPTIONS Features Pricing Market data Gift plans TRADING Overview Brokers Brokers comparison The Leap SPECIAL OFFERS CME Group futures Eurex futures US stocks bundle ABOUT COMPANY Who we are Space mission Blog Help Center Careers Media kit MERCH TradingView store Tarot cards for traders The C63 TradeTime POLICIES & SECURITY Terms of Use Disclaimer Privacy Policy Cookies Policy Accessibility Statement Security tips Bug Bounty program Status page	COMMUNITY Social network Wall of Love Refer a friend Creator program House Rules Moderators IDEAS Trading Education Editors' picks PINE SCRIPT Indicators & strategies Wizards Freelancers Marketplace	BUSINESS SOLUTIONS Widgets Charting libraries Lightweight Charts™ Advanced Charts Trading Platform GROWTH OPPORTUNITIES Advertising Brokerage integration Partner program Education program
---	--	---	--	--

