

飞机组件清单 aircraftComp

GET 导出生产组件

GET /aircraftComp/exportAircraftComp

请求参数

返回示例

文件

```
"craftId": "无人机id",
"comNum": "无人机编号",
"compCode": "组件编码",
"compName": "组件名称",
"materialCode": "物料编码",
"materialName": "物料名称",
"materialDesc": "物料描述",
"compSn": "SN号",
"hardwareVersion": "硬件版本",
"bootloader": "启动引导",
"appSoftware": "应用软件"
```

POST 分页查询无人机组件清单列表

POST /aircraftComp/selectAircraftCompByPage/{pageNum}/{pageSize}

Body 请求参数

```
{
  "craftId": "无人机id",
  "comNum": "无人机编号",
  "compCode": "组件编码",
  "compName": "组件名称",
  "materialCode": "物料编码",
  "materialName": "物料名称",
  "materialDesc": "物料描述",
  "compSn": "SN号",
  "hardwareVersion": "硬件版本",
  "bootloader": "启动引导",
  "appSoftware": "应用软件"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": [
    {
      "craftId": "无人机id",
      "comNum": "无人机编号",
      "compCode": "组件编码",
      "compName": "组件名称",
      "materialCode": "物料编码",
      "materialName": "物料名称",
      "materialDesc": "物料描述",
      "compSn": "SN号",
      "hardwareVersion": "硬件版本",
      "bootloader": "启动引导",
      "appSoftware": "应用软件"
    }
  ]
}
```

POST 获取飞机组件详情

POST /aircraftComp/selectDetail

Body 请求参数

```
{
  "id": "id",
  "comNum": "无人机编号",
  "compCode": "组件编码"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj":
    {
      "craftId": "无人机id",
```

```
        "comNum": "无人机编号",
        "compCode": "组件编码",
        "compName": "组件名称",
        "materialCode": "物料编码",
        "materialName": "物料名称",
        "materialDesc": "物料描述",
        "compSn": "SN号",
        "hardwareVersion": "硬件版本",
        "bootloader": "启动引导",
        "appSoftware": "应用软件"
    }
}
```

POST 分页查询飞机组件清单变更

POST /aircraftCompLog/selectAircraftCompLogByPage/{pageNum}/{pageSize}

Body 请求参数

```
{
  "id": "ID",
  "craftCompId": "无人机组件id",
  "materialCode": "物料编码",
  "compSn": "SN号",
  "hardwareVersion": "硬件版本",
  "bootloader": "启动引导",
  "appSoftware": "应用软件",
  "updateReason": "组件备注",
  "creator": "创建人",
  "createTime": "创建时间",
  "updater": "修改人",
  "updateTime": "修改时"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": {
    "id": "ID",
    "craftCompId": "无人机组件id",
    "materialCode": "物料编码",
```

```
        "compSn": "SN号",
        "hardwareVersion": "硬件版本",
        "bootloader": "启动引导",
        "appSoftware": "应用软件",
        "updateReason": "组件备注",
        "creator": "创建人",
        "createTime": "创建时间",
        "updater": "修改人",
        "updateTime": "修改时"
    }
}
```

POST 【无人机故障】新增

POST /aircraftFault/addFault

Body 请求参数

```
{
  "listName": "所在列表",
  "distAirGround": "是否区分空中地上 true:区分, false不区分",
  "showInAir": "天上是否显示 true:显示 false:不显示",
  "showOnGround": "地上是否显示 true:显示 false:不显示",
  "grade": "",
  "gradeId": "",
  "gradeInAir": "在空中",
  "gradeIdInAir": "在空中",
  "faultTypeId": "错误类型id",
  "faultKey": "故障key",
  "faultValue": "故障值",
  "faultValueInAir": "故障值在空中",
  "faultEnValue": "故障英文值",
  "faultEnValueInAir": "故障英文值在空中",
  "creator": "创建人"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": 1
}
```

POST 【无人机故障分类】新增

POST /aircraftFault/addFaultType

Body 请求参数

```
{
  "name": "名称",
  "remark": "备注",
  "creator": "创建人",
  "languageId": "语言",
  "aircraftTypeIdList": [无人机类型id集合]
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": 1
}
```

POST 【无人机故障对象】新增

POST /aircraftFault/addFaultTypeC

Body 请求参数

```
{
  "name": "名称",
  "remark": "备注",
  "creator": "创建人",
  "languageId": "语言",
  "parentId": "父级id",
  "level": "层级"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
}
```

```
"obj": 1
}
```

POST 故障删除

POST /aircraftFault/delFault/{faultId}?operator =xxx

Path 请求参数

operator = 操作人

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": 1
}
```

POST delFaultType

POST /aircraftFault/delFaultType/{faultTypeId}

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": 1
}
```

POST delFaultTypeC

POST /aircraftFault/delFaultTypeC/{faultTypeId}

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
}
```

```
"obj": 1
}
```

GET 地面站下载translateFile.json文件

GET /aircraftFault/downloadTranslateFile

[返回示例](#)

文件

GET exportFaultCode

GET /aircraftFault/export

[返回示例](#)

文件

GET 导出翻译文件

GET /aircraftFault/exportAsExcel

[返回示例](#)

文件

GET 地面站获取translateFile.json文件信息

GET /aircraftFault/getTranslateFileInfo

[返回示例](#)

文件

POST 【故障码】导入

POST /aircraftFault/import

[文件 JSON](#)

```
{
  "translateList": [
    {
      "type": "",
      "language": "",
      "remark": "",
      "typeKey": [
        1
      ]
    }
  ]
}
```

```

    ],
    "detailList": [
      {
        "name": "",
        "remark": "",
        "mapList1": [
          {
            "key": "",
            "value": "",
            "valueEn": "",
            "grade": "",
            "gradeId": "",
            "distAirGround": "",
            "showInAir": "",
            "showOnGround": "",
            "valueInAir": "",
            "valueEnInAir": "",
            "gradeInAir": ""
          }
        ],
      },
    ],
    "mapList2": [
      {
        "key": "",
        "value": "",
        "valueEn": "",
        "grade": "",
        "gradeId": "",
        "distAirGround": "",
        "showInAir": "",
        "showOnGround": "",
        "valueInAir": "",
        "valueEnInAir": "",
        "gradeInAir": ""
      }
    ]
  }
]
}

```

返回示例

```

{
  "success": true,

```

```
"errorCode": null,
"errorMessage": null,
"date": "yyyy-MM-dd HH:mm:ss",
"obj": 1
}
```

POST 导入翻译文件

POST /aircraftFault/importFromExcel

Body 请求参数

file: 文件

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": 1
}
```

POST 【无人机故障码】列表查询

POST /aircraftFault/selectFaultByPage/{pageNum}/{pageSize}

Body 请求参数

```
{
  "faultKey": "故障key",
  "faultValue": "故障描述"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": {
    "records": [
      {
        "listName": "maplist1 or maplist2",
        "faultKey": "故障编码",

```

```
        "faultValue": "故障解释",
        "faultEnValue": "故障解释英文",
        "creatorName": "创建人",
        "updaterName": "更新人",
        "distAirGround": "区分地面空中 0：不区分,1：区分",
        "showInAir": "空中显示 0：不区分,1：区分",
        "showOnGround": "地面显示 0：不区分,1：区分",
        "gradeIdInAir": "空中等级Id",
        "gradeInAir": "空中等级",
        "faultValueInAir": "空中中文故障描述",
        "faultEnValueInAir": "空中英文故障描述"
    }
},
    "total":1
}
}
```

POST 【语言】列表查询

POST /aircraftFault/selectFaultLanguage

[返回示例](#)

```
{
    "success": true,
    "errorCode": null,
    "errorMessage": null,
    "date": "yyyy-MM-dd HH:mm:ss",
    "obj": {
        "records": [
            {
                "code": "编码",
                "name": "名称",
                "simpleCode": "简码"
            }
        ],
        "total":1
    }
}
```

POST 【无人机故障码大类】列表查询

POST /aircraftFault/selectFaultTypeByPage/{pageNum}/{pageSize}

[Body 请求参数](#)

```
{
  "faultKey": "故障key",
  "faultValue": "故障描述"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": {
    "records": [
      {
        "languageId": "语言id",
        "level": "级别",
        "name": "名称",
        "aircraftTypeId": "机型id",
        "remark": "说明",
        "language": "语言",
        "languageName": "语言名称",
        "creator": "创建人",
        "creatorName": "创建人姓名",
        "updater": "更新人",
        "updaterName": "更新人姓名",
        "createTime": "创建时间",
        "updateTime": "更新时间",
        "hasChild": "是否有子集"
      }
    ],
    "total": 1
  }
}
```

POST 【无人机故障码大类集合】列表查询

POST /aircraftFault/selectFaultTypeCByPage/{pageNum}/{pageSize}

Body 请求参数

```
{
  "parentId": "父级id",
  "faultKey": "故障key",
```

```
"faultValue": "故障描述"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": {
    "records": [
      {
        "languageId": "语言id",
        "level": "级别",
        "name": "名称",
        "aircraftTypeId": "机型id",
        "remark": "说明",
        "language": "语言",
        "languageName": "语言名称",
        "creator": "创建人",
        "creatorName": "创建人姓名",
        "updater": "更新人",
        "updaterName": "更新人姓名",
        "createTime": "创建时间",
        "updateTime": "更新时间",
        "hasChild": "是否有子集"
      }
    ],
    "total": 1
  }
}
```

POST updateFault

POST /aircraftFault/updateFault

Body 请求参数

```
{
  "faultKey": "故障编码",
  "faultValue": "故障解释",
  "faultEnValue": "故障解释英文",
  "creatorName": "创建人",
  "updaterName": "更新人",
  "distAirGround": "区分地面空中 0：不区分，1：区分",
}
```

```
        "showInAir": "空中显示 0：不区分，1：区分",
        "showOnGround": "地面显示 0：不区分，1：区分",
        "gradeIdInAir": "空中等级Id",
        "gradeInAir": "空中等级",
        "faultValueInAir": "空中中文故障描述",
        "faultEnValueInAir": "空中英文故障描述"
    }
}
```

返回示例

```
{
    "success": true,
    "errorCode": null,
    "errorMessage": null,
    "date": "yyyy-MM-dd HH:mm:ss",
    "obj": 1
}
```

POST updateFaultType

POST /aircraftFault/updateFaultType

Body 请求参数

```
{
    "name": "名称",
    "remark": "备注",
    "creator": "创建人",
    "languageId": "语言",
    "aircraftTypeIdList": [无人机类型id集合]
}
```

返回示例

```
{
    "success": true,
    "errorCode": null,
    "errorMessage": null,
    "date": "yyyy-MM-dd HH:mm:ss",
    "obj": 1
}
```

POST updateFaultTypeC

POST /aircraftFault/updateFaultTypeC

Body 请求参数

```
{
  "name": "名称",
  "remark": "备注",
  "creator": "创建人",
  "languageId": "语言",
  "aircraftTypeIdList": [无人机类型id集合]
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": 1
}
```

POST PC端通过Excel文件 新增维保数据

POST /aircraftMaintain/addMaintains

Body 请求参数

```
{
  "creator": "创建人",
  "list": [
    {
      "craftState": "无人机状态",
      "craftId": "无人机id",
      "reportTime": "任务发布时间",
      "comNum": "无人机编号",
      "maintainReason": "维保原因",
      "maintainRemark": "维保说明",
      "compCode": "组件code",
      "compName": "组件名",
      "partName": "原件名",
      "partSn": "原件SN",
      "reportPerson": "发布人id",
      "reportPersonName": "发布人姓名",
      "checkDuplicateMd5": "md5",
      "subMaterialCode": "更换件物料编码",
      "subSn": "更换件物料SN",
      "subMaterialName": "更换件物料名",
      "maintainWay": "维修件处理方式",
    }
  ]
}
```

```
    "hardwareVersion": "硬件版本",
    "softwareVersion": "软件版本",
    "maintainDetail": "维保详情",
    "maintainPerson": "维保人id",
    "maintainPersonName": "维保人姓名",
    "startMaintainTime": "开始维保时间",
    "endMaintainTime": "结束维保时间",
    "examinePerson": "检查人id",
    "examinePersonName": "检查人姓名",
    "tryFlyPerson": "试飞人",
    "tryFly": "是否要求试飞 1是 0否",
    "tryFlyConclusion": "试飞结论",
    "tryFlyPersonName": "试飞人姓名",
    "isMr": ""
  }
]
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": 1
}
```

POST 维保APP端：复制信息查询

POST /aircraftMaintain/copyInfo

Body 请求参数

```
{
  "mtId": "维保任务id"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
```

```
"date": "yyyy-MM-dd HH:mm:ss",
"obj": {
  "mtId": "维保任务主键",
  "taskCode": "维保任务编号",
  "processStage": "维保任务处理阶段",
  "processStageCN": "维保任务处理阶段中文",
  "comNum": "维保任务数量",
  "maintainReason": "维保任务维护原因",
  "maintainReasonCn": "维保任务维护原因中文",
  "compCode": "维保任务公司代码",
  "compName": "维保任务公司名称",
  "taskDetail": "维保任务详情",
  "reportPerson": "维保任务报告人",
  "reportPersonName": "维保任务报告人姓名",
  "reportTime": "维保任务报告时间",
  "partName": "维保任务部件名称",
  "partSn": "维保任务部件序列号",
  "countryName": "维保任务国家名称",
  "provinceName": "维保任务省份名称",
  "cityName": "维保任务城市名称",
  "distName": "维保任务地区名称",
  "subMaterialCode": "维修子材料代码",
  "subMaterialName": "维修子材料名称",
  "subSn": "维修子材料序列号",
  "maintainDetail": "维修详情",
  "receiveTime": "维修接收时间",
  "startMaintainTime": "维修开始时间",
  "endMaintainTime": "维修结束时间",
  "maintainPerson": "维修人员",
  "maintainPersonName": "维修人员姓名",
  "examinePerson": "检验人员",
  "examinePersonName": "检验人员姓名",
  "examTime": "检验时间",
  "examDetail": "检验详情",
  "examConclusion": "检验结论",
  "examConclusionCn": "检验结论中文",
  "tryFly": "试飞状态",
  "tryFlyCn": "试飞状态中文",
  "testFlyPerson": "试飞人员",
  "notTestFlyPerson": "未试飞人员",
  "testFlyPersonName": "试飞人员姓名",
  "notTestFlyPersonName": "未试飞人员姓名",
  "testFlyConclusion": "试飞结论",
  "notTestFlyConclusion": "未试飞结论",
  "craftState": "飞机状态",
```

```
        "craftStateCn": "飞机状态中文",
        "testFlyDetail": "试飞详情",
        "testFlyRemark": "试飞备注",
        "testFlyTime": "试飞时间",
        "notTestFlyTime": "未试飞时间"
    }
}
```

POST 维保APP端：指派数统计

POST /aircraftMaintain/countAssigningNum

Body 请求参数

```
{
  "processStage": "阶段",
  "operatePerson": "操作人"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": 1
}
```

POST 维保APP端：当前飞机故障数量统计(没有完结的维保数)

POST /aircraftMaintain/countMaintainingNum

Body 请求参数

```
{
  "processStage": "阶段",
  "notInMtIdSet": [排除id],
  "craftId": "无人机id"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,

```

```
"date": "yyyy-MM-dd HH:mm:ss",  
"obj": 1  
}
```

GET 维保APP端：飞机维保导出

GET /aircraftMaintain/export

Query 参数

startTime: 开始时间
endTime: 结束时间
maintainReason: 维保人
compName: 组件名
comNum: 组件数量
craftState: 无人机状态
processStage: 阶段
uavTypeCode: 无人机机型code
taskCode: 任务code

返回示例

导出文件，文件的首行就是标题

POST 飞机维保数据预览

POST /aircraftMaintain/importPreview

Body 请求参数

```
{  
  "orderNo": "序号",  
  "comNum": "飞机编号",  
  "maintainReason": "维护原因",  
  "compName": "目标组件",  
  "maintainRemark": "原因说明",  
  "reportPerson": "任务发布人工号",  
  "reportTime": "任务发布时间",  
  "partName": "原件名称",  
  "partSn": "原件SN/批号",  
  "subMaterialCode": "更换件物料代码",  
  "subMaterialName": "更换件名称",  
  "subMaterialNum": "更换件数量",  
  "subSn": "更换件SN/批号",  
  "maintainWay": "维修件处理方式",  
  "hardwareVersion": "硬件版本",  
  "softwareVersion": "软件版本",  
}
```

```
"maintainDetail": "维护记录详情",
"maintainPerson": "维护人工号",
"examinePerson": "检验人工号",
"startMaintainTime": "维护开始时间",
"tryFly": "是否要求试飞",
"tryFlyPerson": "试飞人员工号",
"tryFlyConclusion": "试飞结论",
"endMaintainTime": "维护完成时间",
"craftState": "飞机状态"
}
```

返回示例

```
{
  "records": "",
  "total": "",
  "failureNum": "",
  "successNum": ""
}
```

POST 维保APP端：各个阶段的任务数量统计(待接单、待开始、待维修、待检验、待试飞)

POST /aircraftMaintain/myReportTaskCount

Body 请求参数

```
{
  "operatePerson": "操作人"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": {
    "taskNumInStage1": "",
    "taskNumInStage2": "",
    "taskNumInStage3": "",
    "taskNumInStage4": "",
    "taskNumInStage5": "",
    "taskNumInStage11": ""
  }
}
```

```
}  
}
```

POST 维保APP端：我的数据统计

POST /aircraftMaintain/myStats

Body 请求参数

```
{  
  "maintainPerson": "人"  
}
```

返回示例

```
{  
  "success": true,  
  "errorCode": null,  
  "errorMessage": null,  
  "date": "yyyy-MM-dd HH:mm:ss",  
  "obj": {  
    "serverTime": "服务时间",  
    "maintainNum": "维保次数"  
  }  
}
```

POST 维保APP端：各个阶段的任务数量统计(待接单、待开始、待维修、待检验、待试飞)

POST /aircraftMaintain/myTaskCount

Body 请求参数

```
{  
  "operatePerson": "人"  
}
```

返回示例

```
{  
  "success": true,  
  "errorCode": null,  
  "errorMessage": null,  
  "date": "yyyy-MM-dd HH:mm:ss",  
  "obj": {  
    "taskNumInStage2": "",
```

```
        "taskNumInStage3": "",
        "taskNumInStage4": "",
        "taskNumInStage5": "",
        "taskNumInStage6": ""
    }
}
```

POST 维保APP端：维保全阶段流程查询

POST /aircraftMaintain/processStageShow

Body 请求参数

```
{
  "mtId": "主键"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": {
    "id": "任务的唯一标识符",
    "mtId": "关联的维修任务 ID",
    "processStage": "任务处理阶段",
    "reportTime": "任务发布时间",
    "reportPerson": "任务发布人",
    "reportPersonName": "任务发布人姓名",
    "receiveTime": "接单时间",
    "receivePerson": "接单人",
    "receivePersonName": "接单人姓名",
    "startMaintainTime": "维护开始时间",
    "endMaintainTime": "维护结束时间",
    "maintainPerson": "维护人工号",
    "maintainPersonName": "维护人姓名",
    "examTime": "检验时间",
    "examPerson": "检验人工号",
    "examPersonName": "检验人姓名",
    "tryFly": "是否要求试飞",
    "testFlyTime": "试飞时间",
    "testFlyPerson": "试飞人工号",
    "testFlyPersonName": "试飞人姓名",
    "finshTime": "任务完成时间"
  }
}
```

```
}  
}
```

POST 分页查询无人机维保列表

POST /aircraftMaintain/selectAircraftMaintainByPage/{pageNum}/{pageSize}

Body 请求参数

```
{  
  "taskCode": "任务代码, 模糊匹配",  
  "comNum": "通信编号, 精确匹配",  
  "uavTypeCode": "无人机类型代码, 精确匹配",  
  "startTime": "开始时间, 小于等于报告时间",  
  "endTime": "结束时间, 小于等于报告时间",  
  "maintainReason": "维护原因, 精确匹配",  
  "processStage": "处理阶段, 精确匹配",  
  "craftState": "全局飞行器状态, 精确匹配",  
  "compName": "公司名称, 模糊匹配",  
  "maintainPerson": "维护人员, 模糊匹配"  
}
```

返回示例

```
{  
  "success": true,  
  "errorCode": null,  
  "errorMessage": null,  
  "date": "yyyy-MM-dd HH:mm:ss",  
  "obj": [{  
    "id": "任务ID",  
    "task_code": "任务代码",  
    "process_stage": "处理阶段",  
    "process_stage_cn": "处理阶段中文",  
    "com_num": "组件数量",  
    "uav_type_code": "无人机类型代码",  
    "maintain_reason": "维护原因",  
    "maintain_reason_cn": "维护原因中文",  
    "comp_name": "公司名称",  
    "task_detail": "任务详情",  
    "report_person": "报告人",  
    "report_person_name": "报告人姓名",  
    "report_time": "报告时间",  
    "part_name": "部件名称",  
    "part_sn": "部件序列号",  
    "sub_material_code": "子材料代码",  
  }]
```

```
        "sub_material_name": "子材料名称",
        "sub_sn": "子材料序列号",
        "maintain_detail": "维护详情",
        "start_maintain_time": "开始维护时间",
        "end_maintain_time": "结束维护时间",
        "maintain_person": "维护人员",
        "maintain_person_name": "维护人员姓名",
        "exam_person": "检验人员",
        "exam_person_name": "检验人员姓名",
        "exam_time": "检验时间",
        "exam_detail": "检验详情",
        "exam_conclusion": "检验结论",
        "exam_conclusion_cn": "检验结论中文",
        "try_fly": "试飞",
        "try_fly_cn": "试飞中文",
        "test_fly_detail": "试飞详情",
        "test_fly_remark": "试飞备注",
        "test_fly_person": "试飞人员",
        "test_fly_person_name": "试飞人员姓名",
        "test_fly_conclusion": "试飞结论",
        "test_fly_conclusion_cn": "试飞结论中文",
        "craft_state": "无人机状态",
        "craft_state_cn": "无人机状态中文"
    }
}
]
```

POST 维保APP端：分页查询无人机组件清单列表

POST /aircraftMaintain/selectByPage/{pageNum}/{pageSize}

Body 请求参数

```
{
  "listType": "列表类型，用于选择不同的查询条件分支",
  "comNum": "通信编号，精确匹配",
  "processStage": "处理阶段，精确匹配",
  "provinceCode": "省份代码，精确匹配（父任务或子任务）",
  "cityCode": "城市代码，精确匹配（父任务或子任务）",
  "distCode": "区县代码，精确匹配（父任务或子任务）",
  "orderRule": "排序规则，用于选择升序或降序排序",
  "processStage": "待接单=1,发布完成=1),待开始=2,待维修=3,维修完成=3),待检验=4,检验完成=4),待试飞=5,试飞完成=5),已完成=6,不存在状态=-1;"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": {
    "records": [
      {
        "fileInfos": {
          "diskFile": "磁盘文件路径",
          "fileType": "文件类型",
          "fileName": "文件名"
        },
        "childs": {
          "id": "子任务ID",
          "mtId": "子任务对应的maintain_task_id",
          "parentId": "子任务的父ID",
          "processStage": "子任务的处理阶段",
          "hasChild": "子任务是否有子任务",
          "craftId": "子任务对应的无人机id",
          "comNum": "子任务对应的转成10进制的通讯编号",
          "taskCode": "子任务的任务编码",
          "maintainReason": "子任务的维修原因",
          "maintainReasonCn": "子任务的维修原因中文描述",
          "taskDetail": "子任务的维保任务详情",
          "maintainDetail": "子任务的维护记录详情",
          "globalCraftState": "子任务的飞机全局状态",
          "reportPerson": "子任务的任务发布人",
          "reportPersonName": "子任务的维保任务发布人姓名",
          "ownerPerson": "子任务的拥有者",
          "taskStatus": "子任务的状态 0暂停 1继续",
          "reportTime": "子任务的发布时间",
          "partName": "子任务的原件名称",
          "compName": "子任务的目标组件名称",
          "fileInfos": {
            "diskFile": "子任务的磁盘文件路径",
            "fileType": "子任务的文件类型",
            "fileName": "子任务的文件名"
          }
        }
      }
    ],
    "total": 1
  }
}
```

```
}  
}
```

POST 维保APP端：分页查询可合并列表候选集

POST /aircraftMaintain/selectMergeCandidateByPage/{pageNum}/{pageSize}

Body 请求参数

```
{  
  "listType": "列表类型，用于选择不同的查询条件分支",  
  "comNum": "通信编号，精确匹配",  
  "processStage": "处理阶段，精确匹配",  
  "provinceCode": "省份代码，精确匹配（父任务或子任务）",  
  "cityCode": "城市代码，精确匹配（父任务或子任务）",  
  "distCode": "区县代码，精确匹配（父任务或子任务）",  
  "orderRule": "排序规则，用于选择升序或降序排序",  
  "processStage": "待接单=1,发布完成=1),待开始=2,待维修=3,维修完成=3),待检验=4,检验完成=4),待试飞=5,试飞完成=5),已完成=6,不存在状态=-1;"  
}
```

返回示例

```
{  
  "success": true,  
  "errorCode": null,  
  "errorMessage": null,  
  "date": "yyyy-MM-dd HH:mm:ss",  
  "obj": {  
    "records": [  
      {  
        "fileInfos": {  
          "diskFile": "磁盘文件路径",  
          "fileType": "文件类型",  
          "fileName": "文件名"  
        },  
        "childs": {  
          "id": "子任务ID",  
          "mtId": "子任务对应的maintain_task_id",  
          "parentId": "子任务的父ID",  
          "processStage": "子任务的处理阶段",  
          "hasChild": "子任务是否有子任务",  
          "craftId": "子任务对应的无人机id",  
          "comNum": "子任务对应的转成10进制的通讯编号",  
          "taskCode": "子任务的任务编码",  
          "maintainReason": "子任务的维修原因",  
          "processStage": "子任务的维修阶段"  
        }  
      }  
    ]  
  }  
}
```

```

        "maintainReasonCn": "子任务的维修原因中文描述",
        "taskDetail": "子任务的维保任务详情",
        "maintainDetail": "子任务的维护记录详情",
        "globalCraftState": "子任务的飞机全局状态",
        "reportPerson": "子任务的任务发布人",
        "reportPersonName": "子任务的维保任务发布人姓名",
        "ownerPerson": "子任务的拥有者",
        "taskStatus": "子任务的状态 0暂停 1继续",
        "reportTime": "子任务的发布时间",
        "partName": "子任务的原件名称",
        "compName": "子任务的目标组件名称",
        "fileInfos": {
            "diskFile": "子任务的磁盘文件路径",
            "fileType": "子任务的文件类型",
            "fileName": "子任务的文件名"
        }
    }
}
    ],
    "total":1
}
}

```

POST 维保APP端：分页查询无人机组件清单列表

POST /aircraftMaintain/selectMyMaintainByPage/{pageNum}/{pageSize}

Body 请求参数

```

{
    "listType": "列表类型，用于选择不同的查询条件分支",
    "comNum": "通信编号，精确匹配",
    "processStage": "处理阶段，精确匹配",
    "provinceCode": "省份代码，精确匹配（父任务或子任务）",
    "cityCode": "城市代码，精确匹配（父任务或子任务）",
    "distCode": "区县代码，精确匹配（父任务或子任务）",
    "orderRule": "排序规则，用于选择升序或降序排序",
    "processStage": "待接单=1,发布完成=1),待开始=2,待维修=3,维修完成=3),待检验=4,检验完成=4),待试飞=5,试飞完成=5),已完成=6,不存在状态=-1;"
}

```

返回示例

```

{
    "success": true,
    "errorCode": null,

```

```

"errorMessage": null,
"date": "yyyy-MM-dd HH:mm:ss",
"obj": {
    "records": [
        {
            "fileInfos": {
                "diskFile": "磁盘文件路径",
                "fileType": "文件类型",
                "fileName": "文件名"
            },
            "chilids": {
                "id": "子任务ID",
                "mtId": "子任务对应的maintain_task_id",
                "parentId": "子任务的父ID",
                "processStage": "子任务的处理阶段",
                "hasChild": "子任务是否有子任务",
                "craftId": "子任务对应的无人机id",
                "comNum": "子任务对应的转成10进制的通讯编号",
                "taskCode": "子任务的任务编码",
                "maintainReason": "子任务的维修原因",
                "maintainReasonCn": "子任务的维修原因中文描述",
                "taskDetail": "子任务的维保任务详情",
                "maintainDetail": "子任务的维护记录详情",
                "globalCraftState": "子任务的飞机全局状态",
                "reportPerson": "子任务的任务发布人",
                "reportPersonName": "子任务的维保任务发布人姓名",
                "ownerPerson": "子任务的拥有者",
                "taskStatus": "子任务的状态 0暂停 1继续",
                "reportTime": "子任务的发布时间",
                "partName": "子任务的原件名称",
                "compName": "子任务的目标组件名称",
                "fileInfos": {
                    "diskFile": "子任务的磁盘文件路径",
                    "fileType": "子任务的文件类型",
                    "fileName": "子任务的文件名"
                }
            }
        }
    ],
    "total": 1
}
}

```

POST 维保APP端：分页查询无人机组件清单列表

POST /aircraftMaintain/selectMyReportMaintainByPage/{pageNum}/{pageSize}

Body 请求参数

```
{
  "listType": "列表类型，用于选择不同的查询条件分支",
  "comNum": "通信编号，精确匹配",
  "processStage": "处理阶段，精确匹配",
  "provinceCode": "省份代码，精确匹配（父任务或子任务）",
  "cityCode": "城市代码，精确匹配（父任务或子任务）",
  "distCode": "区县代码，精确匹配（父任务或子任务）",
  "orderRule": "排序规则，用于选择升序或降序排序",
  "processStage": "待接单=1,发布完成=1),待开始=2,待维修=3,维修完成=3),待检验=4,检验完成=4),待试飞=5,试飞完成=5),已完成=6,不存在状态=-1;"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": {
    "records": [
      {
        "fileInfos": {
          "diskFile": "磁盘文件路径",
          "fileType": "文件类型",
          "fileName": "文件名"
        },
        "childs": {
          "id": "子任务ID",
          "mtId": "子任务对应的maintain_task_id",
          "parentId": "子任务的父ID",
          "processStage": "子任务的处理阶段",
          "hasChild": "子任务是否有子任务",
          "craftId": "子任务对应的无人机id",
          "comNum": "子任务对应的转成10进制的通讯编号",
          "taskCode": "子任务的任务编码",
          "maintainReason": "子任务的维修原因",
          "maintainReasonCn": "子任务的维修原因中文描述",
          "taskDetail": "子任务的维保任务详情",
          "maintainDetail": "子任务的维护记录详情",
          "globalCraftState": "子任务的飞机全局状态",
          "reportPerson": "子任务的任务发布人",

```

```
        "reportPersonName": "子任务的维保任务发布人姓名",
        "ownerPerson": "子任务的拥有者",
        "taskStatus": "子任务的状态 0暂停 1继续",
        "reportTime": "子任务的发布时间",
        "partName": "子任务的原件名称",
        "compName": "子任务的目标组件名称",
        "fileInfos": {
            "diskFile": "子任务的磁盘文件路径",
            "fileType": "子任务的文件类型",
            "fileName": "子任务的文件名"
        }
    }
},
    "total":1
}
}
```

POST 维保APP端：任务指派

POST /aircraftMaintain/taskAssign

Body 请求参数

```
{
    "mtId": "",
    "fromPerson": "",
    "fromPersonName": "",
    "toPerson": "",
    "toPersonName": ""
}
```

返回示例

```
{
    "success": true,
    "errorCode": null,
    "errorMessage": null,
    "date": "yyyy-MM-dd HH:mm:ss",
    "obj": null
}
```

POST 维保APP端：任务取消

POST /aircraftMaintain/taskCancel

Body 请求参数

```
{
  "mtId": "任务id",
  "cancelPerson": "取消人"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": null
}
```

POST 维保APP端：任务领取

POST /aircraftMaintain/taskClaim

Body 请求参数

```
{
  "mtId": "任务id"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": null
}
```

POST 维保APP端：继续任务

POST /aircraftMaintain/taskContinue

Body 请求参数

```
{
  "mtId": "任务id",
  "continuePerson": "人"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": null
}
```

POST 维保APP端：各个阶段的任务数量统计(待接单、待开始、待维修、待检验、待试飞)

POST /aircraftMaintain/taskCount

Body 请求参数

```
{
  "countryName": "国家",
  "provinceName": "省",
  "cityName": "市",
  "distName": "区"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": {
    "taskNumInStage1": "",
    "taskNumInStage2": "",
    "taskNumInStage3": "",
    "taskNumInStage4": "",
    "taskNumInStage5": ""
  }
}
```

POST 维保APP端：任务详情查询

POST /aircraftMaintain/taskDetail

Body 请求参数

```
{
  "mtId": "任务id"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": {
    "id": "ID",
    "parentId": "维保任务父ID",
    "mergeSort": "合并任务的排序",
    "craftId": "无人机id",
    "taskCode": "任务编码",
    "maintainReason": "维修原因",
    "taskDetail": "维保任务详情",
    "intentServiceTime": "意向维保时间",
    "countryName": "国家名称",
    "provinceName": "省名称",
    "cityName": "市名称",
    "distName": "区名称",
    "address": "详细地址",
    "compCode": "目标组件编码",
    "partName": "原件名称",
    "compName": "目标组件名称",
    "partSn": "件SN/批次号",
    "globalCraftState": "飞机全局状态",
    "processStage": "任务处理阶段",
    "reportPerson": "任务发布人",
    "reportPersonName": "维保任务发布人姓名",
    "reportTime": "任务发布时间",
    "maintainReasonCn": "维修原因（中文）",
    "comNum": "转成10进制的通讯编号",
    "mtId": "maintain_task_id 维修任务id",
    "fileInfos": "文件信息集合"
  }
}
```

POST 维保APP端：结束任务

POST /aircraftMaintain/taskFinish

Body 请求参数

```
{
  "maintainInfo": [
    {
      "mtId": "维修任务ID",
      "subMaterialCode": "子物料代码",
      "subSn": "子物料序列号",
      "maintainDetail": "维修详情",
      "subMaterialName": "子物料名称",
      "hardwareVersion": "硬件版本",
      "softwareVersion": "软件版本",
      "subMaterialNum": "子物料数量",
      "fileInfos": [
        {
          "diskFile": "磁盘文件路径",
          "fileType": "文件类型",
          "fileName": "文件名"
        }
      ]
    }
  ],
  "maintainPerson": "维护人工号",
  "continuePersonName": "继续操作人姓名",
  "countryCode": "国家代码",
  "provinceCode": "省代码",
  "cityCode": "市代码",
  "distCode": "区代码",
  "address": "详细地址",
  "maintainPersonName": "维护人姓名"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": null
}
```

POST 维保APP端：合并任务

POST /aircraftMaintain/taskMerge

Body 请求参数

```
{
  "mtIds": [],
  "mergePerson": "",
  "mergePersonName": ""
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": null
}
```

POST 维保APP端：暂停任务

POST /aircraftMaintain/taskPause

Body 请求参数

```
{
  "mtId": "任务id",
  "pausePerson": ""
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": null
}
```

POST 维保APP端：任务发布

POST /aircraftMaintain/taskReport

Body 请求参数

```
{
  "comNum": "飞机编码",
  "maintainInfoList": [
    {
      "comNum": "飞机编码",
      "maintainInfoList": "维护信息列表",
      "reportPerson": "报告人",
      "reportPersonName": "报告人姓名",
      "intentServiceTime": "预期服务时间",
      "countryCode": "国家代码",
      "provinceCode": "省份代码",
      "cityCode": "城市代码",
      "distCode": "地区代码",
      "address": "地址",
      "maintainReason": "维护原因"
    }
  ],
  "reportPerson": "报告人",
  "reportPersonName": "报告人姓名",
  "intentServiceTime": "预期服务时间",
  "countryCode": "国家代码",
  "provinceCode": "省份代码",
  "cityCode": "城市代码",
  "distCode": "地区代码",
  "address": "地址",
  "maintainReason": "维护原因"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": null
}
```

POST 维保APP端：任务拆分（取消合并任务）

POST /aircraftMaintain/taskSplit

Body 请求参数

```
{
  "mtId": "",
  "processStage": "待接单=1,发布完成=1),待开始=2,待维修=3,维修完成=3),待检验=4,检验完成=4),待试飞=5,试飞完成=5),已完成=6,不存在状态=-1;",
  "splitPerson": "拆分人"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": null
}
```

POST 维保APP端：开始任务

POST /aircraftMaintain/taskStart

Body 请求参数

```
{
  "mtId": "",
  "processStage": "待接单=1,发布完成=1),待开始=2,待维修=3,维修完成=3),待检验=4,检验完成=4),待试飞=5,试飞完成=5),已完成=6,不存在状态=-1;",
  "startPerson": "启动人"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": null
}
```

POST 维保APP端：任务修改

POST /aircraftMaintain/taskUpdate

Body 请求参数

```
{
  "mtId": "维保任务id",
  "updater": "更新人",
  "comNum": "无人机编号",
  "intentServiceTime": "",
  "countryCode": "国家代码",
  "provinceCode": "省份代码",
  "cityCode": "城市代码",
  "distCode": "区县代码",
  "address": "地址",
  "maintainReason": "原因",
  "maintainInfoList": [
    {
      "fileInfos": {
        "fileName": "文件名"
      },
      "compCode": "组件code",
      "compName": "组件名",
      "partName": "原件名",
      "partSn": "原件SN",
      "taskDetail": "维保任务详情"
    }
  ]
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": null
}
```

GET 维保数据详情

GET /aircraftMaintain/{id}

返回示例

```
{
  "id": 1,
  "craftId": 101,
```

```
"processStage": 2,
"processStageCn": "维护阶段",
"taskCode": "TASK001",
"maintainReason": 1,
"maintainReasonCn": "定期维护",
"maintainRemark": "无异常",
"partName": "发动机",
"compName": "动力部",
"partSn": "SN12345",
"craftState": "正常",
"reportPerson": "张三",
"reportPersonName": "张三",
"reportTime": "2023-10-01 10:00:00",
"taskCountryName": "中国",
"taskProvinceName": "北京市",
"taskCityName": "北京市",
"taskDistName": "海淀区",
"taskAddress": "中关村大街1号",
"subMaterialCode": "MAT001",
"subMaterialName": "润滑油",
"subMaterialNum": 5,
"subSn": "SN67890",
"maintainWay": "人工维护",
"hardwareVersion": "V1.0",
"softwareVersion": "S1.0",
"maintainDetail": "更换润滑油",
"maintainPerson": "李四",
"maintainPersonName": "李四",
"startMaintainTime": "2023-10-02 09:00:00",
"endMaintainTime": "2023-10-02 10:00:00",
"receiveTime": "2023-10-01 11:00:00",
"maintainCountryName": "中国",
"maintainProvinceName": "北京市",
"maintainCityName": "北京市",
"maintainDistName": "海淀区",
"maintainAddress": "中关村大街1号",
"examineTime": "2023-10-03 09:00:00",
"examineDetail": "检查无误",
"examinePerson": "王五",
"examinePersonName": "王五",
"examineConclusion": "合格",
"examineCountryName": "中国",
"examineProvinceName": "北京市",
"examineCityName": "北京市",
"examineDistName": "海淀区",
```

```
"examineAddress": "中关村大街1号",
"tryFly": 1,
"tryFlyConclusion": "成功",
"tryFlyPerson": "赵六",
"tryFlyPersonName": "赵六",
"tryFlyRemark": "飞行正常",
"tryFlyDetail": "飞行高度1000米",
"tryFlyTime": "2023-10-04 10:00:00",
"tryFlyCountryName": "中国",
"tryFlyProvinceName": "北京市",
"tryFlyCityName": "北京市",
"tryFlyDistName": "海淀区",
"tryFlyAddress": "中关村大街1号",
"taskFileNames": [
  {
    "taskFileName": "task1.pdf",
    "taskDiskFile": "/path/to/task1.pdf",
    "taskMtType": 1
  }
],
"maintainFileNames": [
  {
    "maintainFileName": "maintain1.pdf",
    "maintainDiskFile": "/path/to/maintain1.pdf",
    "maintainMtType": 1
  }
],
"examineFileNames": [
  {
    "examineFileName": "examine1.pdf",
    "examineDiskFile": "/path/to/examine1.pdf",
    "examineMtType": 1
  }
],
"tryFlyFileNames": [
  {
    "tryFlyFileName": "tryFly1.pdf",
    "tryFlyDiskFile": "/path/to/tryFly1.pdf",
    "tryFlyMtType": 1
  }
]
}
```

POST 【无人机老化任务】新增

POST /aircraftOldTask/addAircraftOldTask

Body 请求参数

```
{
  "id": "主键ID",
  "taskCode": "任务编号",
  "status": "任务状态 1:进行中 2:已结束",
  "typeId": "老化机型ID",
  "typeCode": "老化机型编号",
  "uavNum": "飞机数量",
  "oldTime": "老化时长 (单位小时)",
  "model": "油门模式 1:默认油门 2:指定油门",
  "minPower": "最小值动力",
  "maxPower": "最大值动力",
  "creator": "创建人",
  "createName": "创建人名称",
  "createTm": "创建时间",
  "comNums": "",
  "components": "",
  "aircraftOldTaskDetailList": [
    {
      "id": "主键ID",
      "taskId": "老化任务ID",
      "comNum": "无人机编码",
      "status": "任务状态 1:进行中 2:已完成 3:断联 4:已停止 5:失败",
      "startTm": "开始时间",
      "endTm": "结束时间",
      "oldTotalTm": "老化总时长",
      "faultList": "故障列表",
      "noticeList": "断连列表"
    }
  ],
  "agingConfList": "老化参数配置"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
}
```

```
"obj": null
}
```

GET 导出无人机老化任务

GET /aircraftOldTask/exportAircraftOldTask

请求参数

[返回示例](#)

导出文件字段含义：

id：主键ID，
taskCode：任务编号，
status：任务状态 1:进行中 2:已结束，
typeId：老化机型ID，
typeCode：老化机型编号，
uavNum：飞机数量，
oldTime：老化时长（单位小时），
model：油门模式 1:默认油门 2:指定油门，
minPower：最小值动力，
maxPower：最大值动力，
creator：创建人，
createName：创建人名称，
createTm：创建时间，
id：主键ID，
taskId：老化任务ID，
comNum：无人机编码，
status：任务状态 1:进行中 2:已完成 3:断联 4:已停止 5:失败，
startTm：开始时间，
endTm：结束时间，
oldTotalTm：老化总时长，
faultList：故障列表，
noticeList：断连列表
agingConfList：老化参数配置

POST 无人机老化任务详情列表查询

POST /aircraftOldTask/selectAircraftOldTaskDetailListByTaskId

[Body 请求参数](#)

```
{
    "taskId":""
}
```

```
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": [
    {
      "id": "主键ID",
      "taskId": "老化任务ID",
      "comNum": "无人机编码",
      "status": "任务状态 1:进行中 2:已完成 3:断联 4:已停止 5:失败",
      "startTm": "开始时间",
      "endTm": "结束时间",
      "oldTotalTm": "老化总时长",
      "faultList": "故障列表",
      "noticeList": "断连列表"
    }
  ]
}
```

POST 【无人机老化任务】列表查询

POST /aircraftOldTask/selectAircraftOldTaskList/{pageNum}/{pageSize}

Body 请求参数

```
{
  "taskCode": "任务编码",
  "status": "任务状态",
  "comNum": "无人机编码",
  "uavStatus": "无人机状态",
  "id": "主键ID",
  "startTm": "开始时间",
  "endTm": "结束时间",
  "typeId": "类型ID",
  "typeCode": "类型编码"
}
```

返回示例

```
{
  "success": true,
```

```
"errorCode": null,
"errorMessage": null,
"date": "yyyy-MM-dd HH:mm:ss",
"obj": [
  {
    "id": "主键ID",
    "taskCode": "任务编号",
    "status": "任务状态 1:进行中 2:已结束",
    "typeId": "老化机型ID",
    "typeCode": "老化机型编号",
    "uavNum": "飞机数量",
    "oldTime": "老化时长（单位小时）",
    "model": "油门模式 1:默认油门 2:指定油门",
    "minPower": "最小值动力",
    "maxPower": "最大值动力",
    "creator": "创建人",
    "createName": "创建人名称",
    "createTm": "创建时间",
    "comNums": ""
  }
]
```

GET 查询无人机老化状态

GET /aircraftOldTask/selectUavOldStatus

请求参数

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": 1
}
```

POST 修改无人机老化任务详情状态

POST /aircraftOldTask/updateAircraftOldTaskDetailStatus

Body 请求参数

```
{
  "id": "主键ID",
  "taskId": "老化任务ID",
  "comNum": "无人机编码",
  "status": "任务状态 1:进行中 2:已完成 3:断联 4:已停止 5:失败",
  "startTm": "开始时间",
  "endTm": "结束时间",
  "oldTotalTm": "老化总时长",
  "faultList": "故障列表",
  "noticeList": "断连列表"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": 1
}
```

POST 新增无人机机型

POST /aircraftType/addAircraftType

Body 请求参数

```
{
  "id": "主键ID",
  "code": "机型代码",
  "name": "机型名称",
  "typeVersion": "机型版本",
  "type": "机型类别tt_sys_dict(8)",
  "typeCode": "类别代码",
  "typeGrade": "机型等级 微型(起飞重量≤250g)、轻型(起飞重量≤7kg)、小型(起飞重量≤25kg)、中型(起飞重量≤150kg)、大型(起飞重量>150kg)",
  "manufacturer": "厂商",
  "manufacturerAddress": "生产厂商地址",
  "licence": "许可证",
  "registerComponentCode": "注册绑定组件类型",
  "registerComponentName": "注册绑定组件名称",
  "emptyWeight": "空机重量 KG",
  "maxTakeoffWeight": "最大起飞重量 KG",
  "cruisingSpeed": "巡航速度m/s",
}
```

"minCruisingSpeed": "最小巡航速度m/s",
"maxCruisingSpeed": "最大巡航速度m/s",
"verticalTakeoffSpeed": "垂直起飞速度 m/s",
"verticalLandingSpeed": "垂直降落速度 m/s",
"maxRange": "最大航程 KM",
"maxCruisingTime": "最大巡航时间,分钟",
"maxTakeoffHeight": "最大飞行高度 M",
"protectionLevel": "防护性能等级(级) 前两位默认IP,后面两位数字允许填写1-9数字或X",
"windResistance": "抗风性能(级)",
"fwWindResistance": "固定翼抗风性能",
"minOperatingTemperature": "最小温度(℃)",
"maxOperatingTemperature": "最大温度(℃)",
"maxOperatingHumidity": "最大湿度%",
"maxLight": "最大光照强度lx",
"maxRainfall": "最大降雨量mm/h",
"maxSnowfall": "最大降雪量mm/h",
"createEmp": "创建人",
"createTm": "创建时间",
"updateEmp": "修改人",
"updateTm": "修改时间",
"isDelete": "删除状态 是Y 否N",
"warningAreaRadius": "警告区半径(米)",
"exitBoundaryRadius": "出场边界半径(米)",
"minProtectBoundaryRadius": "空域保护边界内半径(米)",
"maxProtectBoundaryRadius": "空域保护边界外半径(米)",
"approachCheckBoundaryRadius": "降落场可用检测半径",
"disPatchEnableBoundaryRadius": "降落场入侵距离",
"isPreFlightCheck": "是否需要航前检:0-是|1-否",
"isCheckFault": "融合故障检测:1是|2否,默认2",
"relaDispatchRadius": "关联起降场半径(m)",
"priorLandingElec": "优先降落剩余电量(mAH)",
"priorLandingWait": "优先降落悬停等待时间(s)",
"fhposDeviationRemind": "固定翼(fix-wing)水平位置偏差提醒 m",
"fhposDeviationWarn": "固定翼(fix-wing)水平位置偏差警告 m",
"fvposDeviationRemind": "固定翼(fix-wing)高度位置偏差提醒 m",
"fvposDeviationWarn": "固定翼(fix-wing)高度位置偏差警告 m",
"mhposDeviationRemind": "多旋翼(multirotor)水平位置偏差提醒 m",
"mhposDeviationWarn": "多旋翼(multirotor)水平位置偏差警告 m",
"mvposDeviationRemind": "多旋翼(multirotor)高度位置偏差提醒 m",
"mvposDeviationWarn": "多旋翼(multirotor)高度位置偏差警告 m",
"recVupSpeed": "建议(修正)垂直上升速度(m/s)",
"recVdownSpeed": "建议(修正)垂直下降速度(m/s)",
"recCruisingSpeed": "建议(修正)巡航速度(m/s)",
"lifespanFlyHour": "过寿飞行小时(h)",
"lifespanFlyCycle": "过寿飞行循环",

```
"lifespanFlyMileage": "过寿飞行里程 ( km )",
"lifespanFlyCalendar": "过寿日历时间 ( 天 )",
"gpsLimitDistance": "起降距离限制(GPS)",
"rtkLimitDistance": "起降距离限制(RTK)",
"gpsLimitHeight": "起降高度限制(GPS)",
"rtkLimitHeight": "起降高度限制(RTK)",
"rtkCdsExt": "爬升下降段的外延距离长度 ( RTK ) Y",
"gpsCdsExt": "爬升下降段的外延距离长度 ( GPS ) Y",
"rtkTlCylinderRadius": "垂直起降阶段的圆柱包络体 ( RTK ) R",
"gpsTlCylinderRadius": "垂直起降阶段的圆柱包络体 ( GPS ) R",
"rtkDispatchFlyDistance": "起降场RTK航程",
"rtkCruiseCapsuleUpperh": "巡航阶段胶囊上层高 ( RTK ) H1",
"gpsCruiseCapsuleUpperh": "巡航阶段胶囊上层高 ( GPS ) H1",
"rtkCruiseCapsuleLowerh": "巡航阶段胶囊下层高 ( RTK ) H4",
"gpsCruiseCapsuleLowerh": "巡航阶段胶囊下层高 ( GPS ) H4",
"rtkCruiseCapsuleHoriz": "巡航阶段胶囊水平浮动 ( RTK ) L",
"gpsCruiseCapsuleHoriz": "巡航阶段胶囊水平浮动 ( GPS ) L",
"rtkCruiseCapsuleExt": "巡航阶段胶囊外延 ( RTK ) X",
"gpsCruiseCapsuleExt": "巡航阶段胶囊外延 ( GPS ) X",
"isExternal": "是否是外部机型 0否 1是",
"uomUavType": "uom机型代码"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": 1
}
```

GET 关联起降场初始化

GET /aircraftType/relaDispatchInit/token/{token}

请求参数

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
```

```
"obj": 1
}
```

POST 移除无人机类型

POST /aircraftType/removeAircraftType

Body 请求参数

```
{
  "id": "主键"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": 1
}
```

POST 机型配置的老化参数

POST /aircraftType/selectAgingConfByAircraftType/{AircraftTypeId}

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": {
    "agingConfList": [
      {
        "id": "主键ID",
        "aircraft_type_id": "关联机型id",
        "agingCode": "老化代码",
        "agingName": "老化名称",
        "cmd1": "老化命令参数1",
        "cmd2": "老化命令参数2",
        "input_limit_min": "命令参数最小值",
        "input_limit_max": "命令参数最大值"
      }
    ]
  }
}
```

```
}  
}
```

POST 分页查询无人机机型

POST /aircraftType/selectAircraftType/{pageNum}/{pageSize}

Body 请求参数

```
{  
  "name": "机型名",  
  "type": "类型",  
  "typeCode": "类型编号",  
  "typeVersion": "类型版本"  
}
```

返回示例

```
{  
  "success": true,  
  "errorCode": null,  
  "errorMessage": null,  
  "date": "yyyy-MM-dd HH:mm:ss",  
  "obj": [  
    {  
      "id": "主键ID",  
      "code": "机型代码",  
      "name": "机型名称",  
      "typeVersion": "机型版本",  
      "type": "机型类别tt_sys_dict(8)",  
      "typeCode": "类别代码",  
      "typeGrade": "机型等级 微型 ( 起飞重量≤250g )、轻型 ( 起飞重量≤7kg )、小型 ( 起飞重量≤25kg )、中型 ( 起飞重量≤150kg )、大型 ( 起飞重量 > 150kg )",  
      "manufacturer": "厂商",  
      "manufacturerAddress": "生产厂商地址",  
      "licence": "许可证",  
      "registerComponentCode": "注册绑定组件类型",  
      "registerComponentName": "注册绑定组件名称",  
      "emptyWeight": "空机重量 KG",  
      "maxTakeoffWeight": "最大起飞重量 KG",  
      "cruisingSpeed": "巡航速度m/s",  
      "minCruisingSpeed": "最小巡航速度m/s",  
      "maxCruisingSpeed": "最大巡航速度m/s",  
      "verticalTakeoffSpeed": "垂直起飞速度 m/s",  
      "verticalLandingSpeed": "垂直降落速度 m/s",  
      "maxRange": "最大航程 KM",
```

"maxCruisingTime": "最大巡航时间,分钟",
"maxTakeoffHeight": "最大飞行高度 M",
"protectionLevel": "防护性能等级(级) 前两位默认IP, 后面两位数字允许填写1-9数字或X",
"windResistance": "抗风性能(级)",
"fwWindResistance": "固定翼抗风性能",
"minOperatingTemperature": "最小温度(°C)",
"maxOperatingTemperature": "最大温度(°C)",
"maxOperatingHumidity": "最大湿度%",
"maxLight": "最大光照强度lx",
"maxRainfall": "最大降雨量mm/h",
"maxSnowfall": "最大降雪量mm/h",
"createEmp": "创建人",
"createTm": "创建时间",
"updateEmp": "修改人",
"updateTm": "修改时间",
"isDelete": "删除状态 是Y 否N",
"warningAreaRadius": "警告区半径(米)",
"exitBoundaryRadius": "出场边界半径(米)",
"minProtectBoundaryRadius": "空域保护边界内半径(米)",
"maxProtectBoundaryRadius": "空域保护边界外半径(米)",
"approachCheckBoundaryRadius": "降落场可用检测半径",
"disPatchEnableBoundaryRadius": "降落场入侵距离",
"isPreFlightCheck": "是否需要航前检:0-是|1-否",
"isCheckFault": "融合故障检测:1是|2否, 默认2",
"relaDispatchRadius": "关联起降场半径(m)",
"priorLandingElec": "优先降落剩余电量(mAH)",
"priorLandingWait": "优先降落悬停等待时间(s)",
"fhposDeviationRemind": "固定翼(fix-wing)水平位置偏差提醒 m",
"fhposDeviationWarn": "固定翼(fix-wing)水平位置偏差警告 m",
"fvposDeviationRemind": "固定翼(fix-wing)高度位置偏差提醒 m",
"fvposDeviationWarn": "固定翼(fix-wing)高度位置偏差警告 m",
"mhposDeviationRemind": "多旋翼(multicopter)水平位置偏差提醒 m",
"mhposDeviationWarn": "多旋翼(multicopter)水平位置偏差警告 m",
"mvposDeviationRemind": "多旋翼(multicopter)高度位置偏差提醒 m",
"mvposDeviationWarn": "多旋翼(multicopter)高度位置偏差警告 m",
"recVupSpeed": "建议(修正)垂直上升速度(m/s)",
"recVdownSpeed": "建议(修正)垂直下降速度(m/s)",
"recCruisingSpeed": "建议(修正)巡航速度(m/s)",
"lifespanFlyHour": "过寿飞行小时(h)",
"lifespanFlyCycle": "过寿飞行循环",
"lifespanFlyMileage": "过寿飞行里程(km)",
"lifespanFlyCalendar": "过寿日历时间(天)",
"gpsLimitDistance": "起降距离限制(GPS)",
"rtkLimitDistance": "起降距离限制(RTK)",
"gpsLimitHeight": "起降高度限制(GPS)",

```

        "rtkLimitHeight": "起降高度限制(RTK)",
        "rtkCdsExt": "爬升下降段的外延距离长度 ( RTK ) Y",
        "gpsCdsExt": "爬升下降段的外延距离长度 ( GPS ) Y",
        "rtkTlCylinderRadius": "垂直起降阶段的圆柱包络体 ( RTK ) R",
        "gpsTlCylinderRadius": "垂直起降阶段的圆柱包络体 ( GPS ) R",
        "rtkDispatchFlyDistance": "起降场RTK航程",
        "rtkCruiseCapsuleUpperh": "巡航阶段胶囊上层高 ( RTK ) H1",
        "gpsCruiseCapsuleUpperh": "巡航阶段胶囊上层高 ( GPS ) H1",
        "rtkCruiseCapsuleLowerh": "巡航阶段胶囊下层高 ( RTK ) H4",
        "gpsCruiseCapsuleLowerh": "巡航阶段胶囊下层高 ( GPS ) H4",
        "rtkCruiseCapsuleHoriz": "巡航阶段胶囊水平浮动 ( RTK ) L",
        "gpsCruiseCapsuleHoriz": "巡航阶段胶囊水平浮动 ( GPS ) L",
        "rtkCruiseCapsuleExt": "巡航阶段胶囊外延 ( RTK ) X",
        "gpsCruiseCapsuleExt": "巡航阶段胶囊外延 ( GPS ) X",
        "isExternal": "是否是外部机型 0否 1是",
        "uomUavType": "uom机型代码"
    }
}
]
}

```

POST 查询无人机机型详情

POST /aircraftType/selectAircraftTypeDetail

Body 请求参数

```

{
  "id":""
}

```

返回示例

```

{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj":
    {
      "id": "主键ID",
      "code": "机型代码",
      "name": "机型名称",
      "typeVersion": "机型版本",
      "type": "机型类别tt_sys_dict(8)",
      "typeCode": "类别代码",
      "typeGrade": "机型等级 微型 ( 起飞重量≤250g )、轻型 ( 起飞重量≤7kg )、小型 ( 起飞重量≤25

```

kg)、中型(起飞重量≤150kg)、大型(起飞重量>150kg)",

"manufacturer": "厂商",

"manufacturerAddress": "生产厂商地址",

"licence": "许可证",

"registerComponentCode": "注册绑定组件类型",

"registerComponentName": "注册绑定组件名称",

"emptyWeight": "空机重量 KG",

"maxTakeoffWeight": "最大起飞重量 KG",

"cruisingSpeed": "巡航速度m/s",

"minCruisingSpeed": "最小巡航速度m/s",

"maxCruisingSpeed": "最大巡航速度m/s",

"verticalTakeoffSpeed": "垂直起飞速度 m/s",

"verticalLandingSpeed": "垂直降落速度 m/s",

"maxRange": "最大航程 KM",

"maxCruisingTime": "最大巡航时间,分钟",

"maxTakeoffHeight": "最大飞行高度 M",

"protectionLevel": "防护性能等级(级) 前两位默认IP,后面两位数字允许填写1-9数字或X",

"windResistance": "抗风性能(级)",

"fwWindResistance": "固定翼抗风性能",

"minOperatingTemperature": "最小温度(℃)",

"maxOperatingTemperature": "最大温度(℃)",

"maxOperatingHumidity": "最大湿度%",

"maxLight": "最大光照强度lx",

"maxRainfall": "最大降雨量mm/h",

"maxSnowfall": "最大降雪量mm/h",

"createEmp": "创建人",

"createTm": "创建时间",

"updateEmp": "修改人",

"updateTm": "修改时间",

"isDelete": "删除状态 是Y 否N",

"warningAreaRadius": "警告区半径(米)",

"exitBoundaryRadius": "出场边界半径(米)",

"minProtectBoundaryRadius": "空域保护边界内半径(米)",

"maxProtectBoundaryRadius": "空域保护边界外半径(米)",

"approachCheckBoundaryRadius": "降落场可用检测半径",

"disPatchEnableBoundaryRadius": "降落场入侵距离",

"isPreFlightCheck": "是否需要航前检:0-是|1-否",

"isCheckFault": "融合故障检测:1是|2否,默认2",

"relaDispatchRadius": "关联起降场半径(m)",

"priorLandingElec": "优先降落剩余电量(mAH)",

"priorLandingWait": "优先降落悬停等待时间(s)",

"fhposDeviationRemind": "固定翼(fix-wing)水平位置偏差提醒 m",

"fhposDeviationWarn": "固定翼(fix-wing)水平位置偏差警告 m",

"fvposDeviationRemind": "固定翼(fix-wing)高度位置偏差提醒 m",

"fvposDeviationWarn": "固定翼(fix-wing)高度位置偏差警告 m",

```
"mhposDeviationRemind": "多旋翼(multicopter)水平位置偏差提醒 m",
"mhposDeviationWarn": "多旋翼(multicopter)水平位置偏差警告 m",
"mvposDeviationRemind": "多旋翼(multicopter)高度位置偏差提醒 m",
"mvposDeviationWarn": "多旋翼(multicopter)高度位置偏差警告 m",
"recVupSpeed": "建议(修正)垂直上升速度(m/s)",
"recVdownSpeed": "建议(修正)垂直下降速度(m/s)",
"recCruisingSpeed": "建议(修正)巡航速度(m/s)",
"lifespanFlyHour": "过寿飞行小时(h)",
"lifespanFlyCycle": "过寿飞行循环",
"lifespanFlyMileage": "过寿飞行里程(km)",
"lifespanFlyCalendar": "过寿日历时间(天)",
"gpsLimitDistance": "起降距离限制(GPS)",
"rtkLimitDistance": "起降距离限制(RTK)",
"gpsLimitHeight": "起降高度限制(GPS)",
"rtkLimitHeight": "起降高度限制(RTK)",
"rtkCdsExt": "爬升下降段的外延距离长度(RTK)Y",
"gpsCdsExt": "爬升下降段的外延距离长度(GPS)Y",
"rtkTlCylinderRadius": "垂直起降阶段的圆柱包络体(RTK)R",
"gpsTlCylinderRadius": "垂直起降阶段的圆柱包络体(GPS)R",
"rtkDispatchFlyDistance": "起降场RTK航程",
"rtkCruiseCapsuleUpperh": "巡航阶段胶囊上层高(RTK)H1",
"gpsCruiseCapsuleUpperh": "巡航阶段胶囊上层高(GPS)H1",
"rtkCruiseCapsuleLowerh": "巡航阶段胶囊下层高(RTK)H4",
"gpsCruiseCapsuleLowerh": "巡航阶段胶囊下层高(GPS)H4",
"rtkCruiseCapsuleHoriz": "巡航阶段胶囊水平浮动(RTK)L",
"gpsCruiseCapsuleHoriz": "巡航阶段胶囊水平浮动(GPS)L",
"rtkCruiseCapsuleExt": "巡航阶段胶囊外延(RTK)X",
"gpsCruiseCapsuleExt": "巡航阶段胶囊外延(GPS)X",
"isExternal": "是否是外部机型 0否 1是",
"uomUavType": "uom机型代码"
}
```

```
}
```

POST 下拉选择无人机机型

POST /aircraftType/selectAircraftTypeList

Body 请求参数

```
{
  "name": "机型名",
  "type": "类型",
  "typeCode": "类型编号",
```

```
"typeVersion": "类型版本"
}
```

返回示例

```
{
  "success": true,
  "errorCode": null,
  "errorMessage": null,
  "date": "yyyy-MM-dd HH:mm:ss",
  "obj": [
    {
      "id": "主键ID",
      "code": "机型代码",
      "name": "机型名称",
      "typeVersion": "机型版本",
      "type": "机型类别tt_sys_dict(8)",
      "typeCode": "类别代码",
      "typeGrade": "机型等级 微型（起飞重量≤250g）、轻型（起飞重量≤7kg）、小型（起飞重量≤25kg）、中型（起飞重量≤150kg）、大型（起飞重量>150kg）",
      "manufacturer": "厂商",
      "manufacturerAddress": "生产厂商地址",
      "licence": "许可证",
      "registerComponentCode": "注册绑定组件类型",
      "registerComponentName": "注册绑定组件名称",
      "emptyWeight": "空机重量 KG",
      "maxTakeoffWeight": "最大起飞重量 KG",
      "cruisingSpeed": "巡航速度m/s",
      "minCruisingSpeed": "最小巡航速度m/s",
      "maxCruisingSpeed": "最大巡航速度m/s",
      "verticalTakeoffSpeed": "垂直起飞速度 m/s",
      "verticalLandingSpeed": "垂直降落速度 m/s",
      "maxRange": "最大航程 KM",
      "maxCruisingTime": "最大巡航时间,分钟",
      "maxTakeoffHeight": "最大飞行高度 M",
      "protectionLevel": "防护性能等级(级) 前两位默认IP, 后面两位数字允许填写1-9数字或X",
      "windResistance": "抗风性能(级)",
      "fwWindResistance": "固定翼抗风性能",
      "minOperatingTemperature": "最小温度(℃)",
      "maxOperatingTemperature": "最大温度(℃)",
      "maxOperatingHumidity": "最大湿度%",
      "maxLight": "最大光照强度lx",
      "maxRainfall": "最大降雨量mm/h",
      "maxSnowfall": "最大降雪量mm/h",
      "createEmp": "创建人",
    }
  ]
}
```

"createTm": "创建时间",
"updateEmp": "修改人",
"updateTm": "修改时间",
"isDelete": "删除状态 是Y 否N",
"warningAreaRadius": "警告区半径(米)",
"exitBoundaryRadius": "出场边界半径(米)",
"minProtectBoundaryRadius": "空域保护边界内半径(米)",
"maxProtectBoundaryRadius": "空域保护边界外半径(米)",
"approachCheckBoundaryRadius": "降落场可用检测半径",
"disPatchEnableBoundaryRadius": "降落场入侵距离",
"isPreFlightCheck": "是否需要航前检:0-是|1-否",
"isCheckFault": "融合故障检测:1是|2否, 默认2",
"relaDispatchRadius": "关联起降场半径(m)",
"priorLandingElec": "优先降落剩余电量(mAH)",
"priorLandingWait": "优先降落悬停等待时间(s)",
"fhposDeviationRemind": "固定翼(fix-wing)水平位置偏差提醒 m",
"fhposDeviationWarn": "固定翼(fix-wing)水平位置偏差警告 m",
"fvposDeviationRemind": "固定翼(fix-wing)高度位置偏差提醒 m",
"fvposDeviationWarn": "固定翼(fix-wing)高度位置偏差警告 m",
"mhposDeviationRemind": "多旋翼(multicopter)水平位置偏差提醒 m",
"mhposDeviationWarn": "多旋翼(multicopter)水平位置偏差警告 m",
"mvposDeviationRemind": "多旋翼(multicopter)高度位置偏差提醒 m",
"mvposDeviationWarn": "多旋翼(multicopter)高度位置偏差警告 m",
"recVupSpeed": "建议(修正)垂直上升速度(m/s)",
"recVdownSpeed": "建议(修正)垂直下降速度(m/s)",
"recCruisingSpeed": "建议(修正)巡航速度(m/s)",
"lifespanFlyHour": "过寿飞行小时(h)",
"lifespanFlyCycle": "过寿飞行循环",
"lifespanFlyMileage": "过寿飞行里程(km)",
"lifespanFlyCalendar": "过寿日历时间(天)",
"gpsLimitDistance": "起降距离限制(GPS)",
"rtkLimitDistance": "起降距离限制(RTK)",
"gpsLimitHeight": "起降高度限制(GPS)",
"rtkLimitHeight": "起降高度限制(RTK)",
"rtkCdsExt": "爬升下降段的外延距离长度(RTK)Y",
"gpsCdsExt": "爬升下降段的外延距离长度(GPS)Y",
"rtkTlCylinderRadius": "垂直起降阶段的圆柱包络体(RTK)R",
"gpsTlCylinderRadius": "垂直起降阶段的圆柱包络体(GPS)R",
"rtkDispatchFlyDistance": "起降场RTK航程",
"rtkCruiseCapsuleUpperh": "巡航阶段胶囊上层高(RTK)H1",
"gpsCruiseCapsuleUpperh": "巡航阶段胶囊上层高(GPS)H1",
"rtkCruiseCapsuleLowerh": "巡航阶段胶囊下层高(RTK)H4",
"gpsCruiseCapsuleLowerh": "巡航阶段胶囊下层高(GPS)H4",
"rtkCruiseCapsuleHoriz": "巡航阶段胶囊水平浮动(RTK)L",
"gpsCruiseCapsuleHoriz": "巡航阶段胶囊水平浮动(GPS)L",

```
        "rtkCruiseCapsuleExt": "巡航阶段胶囊外延 ( RTK ) X",
        "gpsCruiseCapsuleExt": "巡航阶段胶囊外延 ( GPS ) X",
        "isExternal": "是否是外部机型 0否 1是",
        "uomUavType": "uom机型代码"
    }
}
]
```

POST 飞机下拉

POST /aircraftType/uavDropList

Body 请求参数

```
{
    "craftTypeId": "类型id"
}
```

返回示例

```
{
    "success": true,
    "errorCode": null,
    "errorMessage": null,
    "date": "yyyy-MM-dd HH:mm:ss",
    "obj": [
        {
            "craftId": "无人机id",
            "comNum": "无人机编号"
        }
    ]
}
```

GET 飞机机型Redis数据重置

GET /aircraftType/uavTypeRedisReset/token/{token}

请求参数

返回示例

```
{
    "success": true,
    "errorCode": null,
    "errorMessage": null,
```

```
"date": "yyyy-MM-dd HH:mm:ss",
"obj": null
}
```

POST 修改无人机机型

POST /aircraftType/updateAircraftType

Body 请求参数

```
{
    "id": "主键ID",
    "code": "机型代码",
    "name": "机型名称",
    "typeVersion": "机型版本",
    "type": "机型类别tt_sys_dict(8)",
    "typeCode": "类别代码",
    "typeGrade": "机型等级 微型（起飞重量≤250g）、轻型（起飞重量≤7kg）、小型（起飞重量≤25kg）、中型（起飞重量≤150kg）、大型（起飞重量>150kg）",
    "manufacturer": "厂商",
    "manufacturerAddress": "生产厂商地址",
    "licence": "许可证",
    "registerComponentCode": "注册绑定组件类型",
    "registerComponentName": "注册绑定组件名称",
    "emptyWeight": "空机重量 KG",
    "maxTakeoffWeight": "最大起飞重量 KG",
    "cruisingSpeed": "巡航速度m/s",
    "minCruisingSpeed": "最小巡航速度m/s",
    "maxCruisingSpeed": "最大巡航速度m/s",
    "verticalTakeoffSpeed": "垂直起飞速度 m/s",
    "verticalLandingSpeed": "垂直降落速度 m/s",
    "maxRange": "最大航程 KM",
    "maxCruisingTime": "最大巡航时间,分钟",
    "maxTakeoffHeight": "最大飞行高度 M",
    "protectionLevel": "防护性能等级(级) 前两位默认IP,后面两位数字允许填写1-9数字或X",
    "windResistance": "抗风性能(级)",
    "fwWindResistance": "固定翼抗风性能",
    "minOperatingTemperature": "最小温度(℃)",
    "maxOperatingTemperature": "最大温度(℃)",
    "maxOperatingHumidity": "最大湿度%",
    "maxLight": "最大光照强度lx",
    "maxRainfall": "最大降雨量mm/h",
    "maxSnowfall": "最大降雪量mm/h",
    "createEmp": "创建人",
    "createTm": "创建时间",
    "updateEmp": "修改人",
}
```

"updateTm": "修改时间",
"isDelete": "删除状态 是Y 否N",
"warningAreaRadius": "警告区半径(米)",
"exitBoundaryRadius": "出场边界半径(米)",
"minProtectBoundaryRadius": "空域保护边界内半径(米)",
"maxProtectBoundaryRadius": "空域保护边界外半径(米)",
"approachCheckBoundaryRadius": "降落场可用检测半径",
"disPatchEnableBoundaryRadius": "降落场入侵距离",
"isPreFlightCheck": "是否需要航前检:0-是|1-否",
"isCheckFault": "融合故障检测:1是|2否,默认2",
"relaDispatchRadius": "关联起降场半径(m)",
"priorLandingElec": "优先降落剩余电量(mAH)",
"priorLandingWait": "优先降落悬停等待时间(s)",
"fhposDeviationRemind": "固定翼(fix-wing)水平位置偏差提醒 m",
"fhposDeviationWarn": "固定翼(fix-wing)水平位置偏差警告 m",
"fvposDeviationRemind": "固定翼(fix-wing)高度位置偏差提醒 m",
"fvposDeviationWarn": "固定翼(fix-wing)高度位置偏差警告 m",
"mhposDeviationRemind": "多旋翼(multirotor)水平位置偏差提醒 m",
"mhposDeviationWarn": "多旋翼(multirotor)水平位置偏差警告 m",
"mvposDeviationRemind": "多旋翼(multirotor)高度位置偏差提醒 m",
"mvposDeviationWarn": "多旋翼(multirotor)高度位置偏差警告 m",
"recVupSpeed": "建议(修正)垂直上升速度(m/s)",
"recVdownSpeed": "建议(修正)垂直下降速度(m/s)",
"recCruisingSpeed": "建议(修正)巡航速度(m/s)",
"lifespanFlyHour": "过寿飞行小时(h)",
"lifespanFlyCycle": "过寿飞行循环",
"lifespanFlyMileage": "过寿飞行里程(km)",
"lifespanFlyCalendar": "过寿日历时间(天)",
"gpsLimitDistance": "起降距离限制(GPS)",
"rtkLimitDistance": "起降距离限制(RTK)",
"gpsLimitHeight": "起降高度限制(GPS)",
"rtkLimitHeight": "起降高度限制(RTK)",
"rtkCdsExt": "爬升下降段的外延距离长度(RTK)Y",
"gpsCdsExt": "爬升下降段的外延距离长度(GPS)Y",
"rtkTlCylinderRadius": "垂直起降阶段的圆柱包络体(RTK)R",
"gpsTlCylinderRadius": "垂直起降阶段的圆柱包络体(GPS)R",
"rtkDispatchFlyDistance": "起降场RTK航程",
"rtkCruiseCapsuleUpperh": "巡航阶段胶囊上层高(RTK)H1",
"gpsCruiseCapsuleUpperh": "巡航阶段胶囊上层高(GPS)H1",
"rtkCruiseCapsuleLowerh": "巡航阶段胶囊下层高(RTK)H4",
"gpsCruiseCapsuleLowerh": "巡航阶段胶囊下层高(GPS)H4",
"rtkCruiseCapsuleHoriz": "巡航阶段胶囊水平浮动(RTK)L",
"gpsCruiseCapsuleHoriz": "巡航阶段胶囊水平浮动(GPS)L",
"rtkCruiseCapsuleExt": "巡航阶段胶囊外延(RTK)X",
"gpsCruiseCapsuleExt": "巡航阶段胶囊外延(GPS)X",

```
        "isExternal": "是否是外部机型 0否 1是",  
        "uomUavType": "uom机型代码"  
    }  
}
```

返回示例

```
{  
    "success": true,  
    "errorCode": null,  
    "errorMessage": null,  
    "date": "yyyy-MM-dd HH:mm:ss",  
    "obj": 1  
}
```