CONFIG NETWORK INTERFACE ON FREEBSD

contoh 2 interface

re0: public

dc0: LAN

1. cek interface "ifconfig -a"

```
padli@padli-desktop: ~
                                          padli@padli-desktop: ~
padli@padli-desktop: ~
                                                                                 ×
root@raisa:/ # ifconfig -a
re0: flags=8843<UP,BROADCAST,RUNNING,SIMPLEX,MULTICAST> metric 0 mtu 1500
        options=8209b<RXCSUM,TXCSUM,VLAN MTU,VLAN HWTAGGING,VLAN HWCSUM,WOL MAGIC,
LINKSTATE>
        ether 10:78:d2:3a:30:60
        inet 192.168.100.10 netmask 0xffffff00 broadcast 192.168.100.255
        nd6 options=29<PERFORMNUD,IFDISABLED,AUTO_LINKLOCAL>
        media: Ethernet autoselect (100baseTX <full-duplex>)
        status: active
dc0: flags=8843<UP,BROADCAST,RUNNING,SIMPLEX,MULTICAST> metric 0 mtu 1500
        options=80008<VLAN_MTU,LINKSTATE>
        ether 00:80:c8:f6:f6:c0
        inet 192.168.0.1 netmask 0xffffff00 broadcast 192.168.0.255
        nd6 options=29<PERFORMNUD, IFDISABLED, AUTO_LINKLOCAL>
        media: Ethernet autoselect (none)
        status: no carrier
loo: flags=8049<UP,LOOPBACK,RUNNING,MULTICAST> metric 0 mtu 16384
        options=600003<RXCSUM,TXCSUM,RXCSUM_IPV6,TXCSUM_IPV6>
        inet6 ::1 prefixlen 128
        inet6 fe80::1%lo0 prefixlen 64 scopeid 0x3
        inet 127.0.0.1 netmask 0xff000000
        nd6 options=21<PERFORMNUD,AUTO_LINKLOCAL>
root@raisa:/ #
```

2. edit "vi /etc/rc.conf" dan save

```
padli@padli-desktop: ~ x padli@padli-desktop: ~ x hostname="raisa"

ifconfig_re0="inet 192.168.100.10 netmask 255.255.255.0"

defaultrouter="192.168.100.1"

ifconfig_dc0="192.168.0.1 netmask 255.255.255.0"

sshd_enable="YES"

# Set dumpdev to "AUTO" to enable crash dumps, "NO" to disable dumpdev="AUTO"

~
```

3. restart network "/etc/netstart"

```
padli@padli-desktop: ~
                                       x padli@padli-desktop: ~
padli@padli-desktop: ~
                                                                                 ×
root@raisa:/ # /etc/netstart
Setting hostuuid: 00020003-0004-0005-0006-000700080009.
Setting hostid: 0x81f4ec68.
Starting Network: lo0 re0 dc0.
loo: flags=8049<UP,LOOPBACK,RUNNING,MULTICAST> metric 0 mtu 16384
        options=600003<RXCSUM,TXCSUM,RXCSUM_IPV6,TXCSUM_IPV6>
        inet6 ::1 prefixlen 128
        inet6 fe80::1%lo0 prefixlen 64 scopeid 0x3
        inet 127.0.0.1 netmask 0xff000000
        nd6 options=21<PERFORMNUD,AUTO_LINKLOCAL>
re0: flags=8843<UP,BROADCAST,RUNNING,SIMPLEX,MULTICAST> metric 0 mtu 1500
        options=8209b<RXCSUM,TXCSUM,VLAN_MTU,VLAN_HWTAGGING,VLAN_HWCSUM,WOL_MAGIC,
LINKSTATE>
        ether 10:78:d2:3a:30:60
        inet 192.168.100.10 netmask 0xffffff00 broadcast 192.168.100.255
        nd6 options=29<PERFORMNUD, IFDISABLED, AUTO_LINKLOCAL>
        media: Ethernet autoselect (100baseTX <full-duplex>)
        status: active
dc0: flags=8843<UP,BROADCAST,RUNNING,SIMPLEX,MULTICAST> metric 0 mtu 1500
        options=80008<VLAN MTU,LINKSTATE>
        ether 00:80:c8:f6:f6:c0
        inet 192.168.0.1 netmask 0xffffff00 broadcast 192.168.0.255
        nd6 options=29<PERFORMNUD, IFDISABLED, AUTO_LINKLOCAL>
```

4. tambahkan nameserver 8.8.8.8 "vi /etc/resolv.conf"

```
padli@padli-desktop: ~

padli@padli-desktop: ~

padli@padli-desktop: ~

padli@padli-desktop: ~

x

padli@padli-desktop: ~

x
```

4. cek interface "ifconfig -a", gateway "netstat -rn", ns "more /etc/resolv.conf"



