	0000000	53	4f	53	20	44	52	56	52	22	05	03	00	43	48	41	52	SOS DRVR"CHAR	000a+ <mark>0522</mark>
	0000010	53 4	45	54	20	20	20	20	20	20	20	20	20	09	0b	0d	29	SET)	052c
	00000020	28 2	28	38	00	06	01	2a	2c	3b	28	28	00	06	01	2a	2c	((8*,;((*,	
	• • •													A					
	00000520	0c	10	14	18	1c	20	8c	8c	b0	2c	b4	b8	00	00	86	0f		0530+ <mark>0f86</mark>
	00000530	00	00	0a	01	80	2e	43	4f	4e	53	4f	4c	45	20	20	20	CONSOLE	14b6
	• • •									_									
	000014b0	00 0	ca	10	f8	60	00	66	04	02	00	a1	00	a3	00	a5	00	`.f	14b8+ <mark>0466</mark>
	000014c0	a9 (00	ac	00	b5	00	bd	00	17	01	2.8	01	2c	01	3a	01		191e
	00001910	f5 (0e	fc	0e	33	0f	36	0f	71	0f	77	0f	7f	0f	00	00	3.6.q.w	
	00001920	22	06	22	00	32	01	0b	2e	43	46	46	41	33	30	30	30	".".2CFFA3000	1922+ <mark>0622</mark>
	00001930	44	31	20	20	20	20	80	01	00	f1	10	00	00	00	53	44	D1SD	1f44
	00001940	00	10	00	0.0	44	00	32	01	0b	2e	43	46	46	41	33	30	D.2CFFA30	·
	• • •				A														
	00001f40	00	06	00	00	18	01	00	00	02	00	22	00	24	00	44	00		1f46+ <mark>0118</mark>
	00001f50	46	00	66	00	68	00	88	0.0	8a	00	aa	00	ac	00	CC	00	F.f.h	205e
															-				
	00002050	68	05	70	05	81	05	89	05	94	05	99	05	af	05	ff	ff	h.p	
	00002060	00	00	00	00	00	00	00	00	00	00	00	00	00	00	00	00		

Black means calculate next jump.

Light Blue is "decision bytes" (Read 2 bytes for calculating bytes (0000) or stop (FFFF).

Light Green is destination of next jump.