


Asset Version: 1.0.0 **Supported pipeline:** URP (Universal) **Unity version:** 6000.0.32f1

First and Third Person Camera System

User manual & setup guide



Developed by: Pcelar Development

Support: pcelar1@gmail.com

Documentation date: December 2025

Table of Contents

• QUICK START GUIDE.....	3
• CUSTOMIZATION GUIDE.....	5
• TROUBLESHOOTING.....	6
• SUPPORT & CONTACT	7
• LICENSE & TERMS.....	8
• VERSION HISTORY	9

QUICK START GUIDE

Follow these steps to test the system immediately after importing.

1.

Opening the Test Scene

The fastest way to see the system in action is to use the pre-configured scene.

- Navigate to **Assets > FirstAndThirdPersonCameraSystem > Scenes**.
- Double-click the **TestScene**.
- Press the **Play** button at the top of the Unity Editor.

2.

Testing the Controls

Once in Play mode, use the following inputs:

- **Movement:** W, A, S, D
- **Sprint:** Hold Left Shift
- **Jump:** Spacebar
- **Look:** Move Mouse
- **Switch Perspective:** While the game is running, select the **Camera Pivot** in the Hierarchy and toggle the **isFirstPerson** checkbox in the Inspector.

3.

Setting Up in Your Own Scene

If you want to add the player to your own existing project, follow this 3-step setup:

Step A: The Environment


- Drag the **Environment** prefab into your scene.
- **Note:** Ensure your ground, walls and ceilings are on a specific **Layer** (e.g., "Environment") for camera collisions to work.

Step B: The Player

- Drag the **FirstAndThirdPerson_player** prefab into your scene.
- Set the Player's Layer to "**Player**".
- Select the **Player**. In the **Inspector**, set the **Ground Mask** layer to the layer your ground is on (e.g., "**Environment**").

Step C: The Camera Settings

- Select the **Camera Pivot** child object.
- In the **FirstAndThirdPersonCamera** script inspector:
 1. Assign your **Main Camera** to the "Main Camera" slot.
 2. Assign the **Capsule** to the "Player" slot.
 3. Under **Collision Layers**, check the box for your "Environment" layer and **uncheck** the "Player" layer.



CUSTOMIZATION GUIDE

You can tweak the feel of the camera and movement directly in the Inspector. You do not need to edit the code.

1. Movement Settings



Select the **Capsule** in the Hierarchy to find these settings in the **PlayerMovement** script:

- **Walk Speed:** How fast the player moves normally.
- **Run Speed:** How fast the player moves when holding Shift.
- **Jump Height:** Adjusts the upward force of the jump.
- **Gravity:** Adjust this if the falling feels too "floaty".

2. Camera Settings

Select the **Camera Pivot** in the Hierarchy to find these settings:

- **Sensitivity:** Increase this for faster mouse look.
- **Orbit Distance:** Adjusts the distance between the camera and the player.
- **Vertical Offset:** Adjust the height of the camera.
- **Horizontal Offset:** Moves the camera to the left or right for an "over-the-shoulder" view.
- **Sphere Radius:** Adjusts the thickness of the camera's collision detection. A larger radius prevents the camera from getting too close to wall edges.



TROUBLESHOOTING

If the system isn't working as expected, check these common fixes:

"The materials are bright pink!"

- **Fix:** This happens if your project isn't set to URP.
- Go to **Edit > Project Settings > Graphics** and drag the **URP Asset** from the `/Settings` folder into the **"Default Render Pipeline"** slot.

"The camera is clipping through the walls/ceiling."

- **Fix:** Ensure your ground, walls, and ceiling have a **Mesh Collider** or **Box Collider** attached.
- Also, check that those objects are on the **"Environment"** layer and that the **"Collision Layer"** mask in the script is set to look for that layer.

"The player won't move."

- **Fix:** Make sure the **CharacterController** component is enabled on the Capsule and that the **GroundCheck** object is positioned correctly at the bottom of the feet.

"The player won't jump."

- **Fix:** Select the **Player**. In the **Inspector**, set the **Ground Mask** layer to the layer your ground is on (e.g., **"Environment"**). If this is not set correctly, the script cannot detect that you are touching the ground to allow a jump.

SUPPORT & CONTACT

Thank you for choosing the **First & Third Person Camera System**. I am committed to improving this asset and would love to hear your feedback.

1. Technical Support

If you encounter any bugs, have questions about integration, or need help with a specific use case, please reach out via email:

- **Email:** [pcelar1@gmail.com]
- **Response Time:** I typically respond within 24-48 hours.

2. Leaving a Review

If this system helped your project, please consider leaving a rating and review on the Unity Asset Store. Reviews are the best way to support independent developers!

LICENSE & TERMS

- **Usage:** This asset is licensed for use in any of your personal or commercial game projects.
- **Redistribution:** You may not resell or redistribute the source code, scripts, or assets included in this package as a standalone product or as part of a template/asset pack.
- **Attribution:** Attribution is not required but is always appreciated.

VERSION HISTORY

v1.0.0 (December 2025) Initial Release of the system.

- Includes **Player Prefab** with a pre-configured Character Controller.
- Includes **Test Scene** with a physics-ready environment.
- Includes **Hybrid Camera System** with First and Third-person toggling.
- Includes **Sphere-cast Collision** logic for smooth camera movement.
- Includes **Environment Prefab** featuring floor, walls, and ceiling.