

Use this cheat sheet for various SQL commands and their syntax, descriptions, and examples.

CREATE TABLE

CREATE TABLE statement is to create the table. Each column in the table is specified with its name, data type and an optional keyword which could be **PRIMARY KEY**, **NOT NULL**, etc.,

Syntax (MySQL/DB2):

```
CREATE TABLE table_name (col1 datatype optional keyword, col2 datatype optional keyword, col3
datatype optional keyword,..., coln datatype optional keyword)
```



Information:

Pressing Tab in the current editor will insert the tab character. Toggle this behavior by pressing Control+M.



Example (MySQL/DB2):

```
CREATE TABLE employee ( employee_id char(2) PRIMARY KEY, first_name varchar(30) NOT NULL, mobile int);
```



Information:

Pressing Tab in the current editor will insert the tab character. Toggle this behavior by pressing Control+M.



ALTER TABLE - ADD COLUMN

ALTER TABLE statement is used to add the columns to a table.

Syntax (MySQL/DB2):

Option 1 -

```
ALTER TABLE table_name ADD column_name_1 datatype....ADD COLUMN column_name_n datatype;
```



Information:

Pressing Tab in the current editor will insert the tab character. Toggle this behavior by pressing Control+M.



Option 2 -

```
ALTER TABLE table_name ADD COLUMN column_name_1 datatype....ADD COLUMN column_name_n datatype  
;
```



Information:

Pressing Tab in the current editor will insert the tab character. Toggle this behavior by pressing Control+M.

**Example (MySQL/DB2):**

Option 1-

```
ALTER TABLE employee ADD income bigint;
```



Information:

Pressing Tab in the current editor will insert the tab character. Toggle this behavior by pressing Control+M.



Option 2 -

```
ALTER TABLE employee ADD COLUMN income bigint;
```



Information:

Pressing Tab in the current editor will insert the tab character. Toggle this behavior by pressing Control+M.



ALTER TABLE - ALTER COLUMN

MySQL: *ALTER TABLE MODIFY* MODIFY clause is used with the ALTER TABLE statement to modify the data type of columns.

Db2: *ALTER TABLE ALTER COLUMN* statement is used to modify the data type of columns.

Syntax:

MySQL -

```
ALTER TABLE table_name MODIFY column_name_1 new_data_type;
```



Information:

Pressing Tab in the current editor will insert the tab character. Toggle this behavior by pressing Control+M.



DB2 -

```
ALTER TABLE table_name ALTER COLUMN column_name_1 SET DATA TYPE datatype;
```



Information:

Pressing Tab in the current editor will insert the tab character. Toggle this behavior by pressing Control+M.



Example:

MySQL -

```
ALTER TABLE employee MODIFY mobile CHAR(20);
```



Information:

Pressing Tab in the current editor will insert the tab character. Toggle this behavior by pressing Control+M.



DB2 -

```
ALTER TABLE employee ALTER COLUMN mobile SET DATA TYPE CHAR(20);
```



Information:

Pressing Tab in the current editor will insert the tab character. Toggle this behavior by pressing Control+M.



ALTER TABLE - DROP COLUMN

ALTER TABLE DROP COLUMN statement is used to remove columns from a table.

Syntax (MySQL/DB2):

```
ALTER TABLE table_name DROP COLUMN column_name_1 ;
```



Information:

Pressing Tab in the current editor will insert the tab character. Toggle this behavior by pressing Control+M.



Example (MySQL/DB2):

```
ALTER TABLE employee DROP COLUMN mobile ;
```



Information:

Pressing Tab in the current editor will insert the tab character. Toggle this behavior by pressing Control+M.



ALTER TABLE - RENAME COLUMN

MySQL: *ALTER TABLE CHANGE COLUMN* CHANGE COLUMN clause is used to rename the columns in a table.

DB2: *ALTER TABLE RENAME COLUMN* statement is used to rename the columns in a table.

Syntax:

MySQL -

```
ALTER TABLE table_name CHANGE COLUMN current_column_name new_column_name datatype [optional keywords];
```



Information:

Pressing Tab in the current editor will insert the tab character. Toggle this behavior by pressing Control+M.



DB2 -

```
ALTER TABLE table_name RENAME COLUMN current_column_name TO new_column_name;
```



Information:

Pressing Tab in the current editor will insert the tab character. Toggle this behavior by pressing Control+M.



Example:

MySQL -

```
ALTER TABLE employee CHANGE COLUMN first_name name VARCHAR(255);
```



Information:

Pressing Tab in the current editor will insert the tab character. Toggle this behavior by pressing Control+M.



DB2 -

```
ALTER TABLE employee RENAME COLUMN first_name TO name;
```



Information:

Pressing Tab in the current editor will insert the tab character. Toggle this behavior by pressing Control+M.



TRUNCATE TABLE

MySQL: *TRUNCATE TABLE* statement is used to delete all of the rows in a table.

DB2: The *IMMEDIATE* specifies to process the statement immediately and that it cannot be undone.

Syntax:

MySQL -

```
TRUNCATE TABLE table_name;
```



Information:

Pressing Tab in the current editor will insert the tab character. Toggle this behavior by pressing Control+M.



DB2 -

```
TRUNCATE TABLE table_name IMMEDIATE;
```

**Information:**

Pressing Tab in the current editor will insert the tab character. Toggle this behavior by pressing Control+M.

**Example:**

MySQL -

```
TRUNCATE TABLE employee;
```

**Information:**

Pressing Tab in the current editor will insert the tab character. Toggle this behavior by pressing Control+M.



DB2 -

```
TRUNCATE TABLE employee IMMEDIATE ;
```

**Information:**

Pressing Tab in the current editor will insert the tab character. Toggle this behavior by pressing Control+M.



DROP TABLE

Use the *DROP TABLE* statement to delete a table from a database. If you delete a table that contains data, by default the data will be deleted alongside the table.

Syntax (MySQL/DB2):

```
DROP TABLE table_name ;
```

**Information:**

Pressing Tab in the current editor will insert the tab character. Toggle this behavior by pressing Control+M.

**Example (MySQL/DB2):**

```
DROP TABLE employee ;
```

**Information:**

Pressing Tab in the current editor will insert the tab character. Toggle this behavior by pressing Control+M.

