The Brown logo and site name (i.e., "Brown CS") stay fixed to the left-hand side of the content container and always appear in the same vertical position, 50px from the top of the page.

The hero image always takes up the full width of the page's content container, regardless of the screen size.

On mobile and tablet, the "News" section appears on top of "Events," "Degrees," and "Blog" so that each takes up the full width of the page's content container. On larger screens, the "News" section always takes up one-third of the width of the page's content container.

On mobile and tablet (where the "News" section appears on top of the "Events," "Degrees," and "Blog" sections in a single column), the last two of the five news headlines currently shown are hidden. These last two headlines appear on all larger screen sizes.

On mobile and tablet, the "Degrees" and "Blog" sections always appear below "Events," with "Degreees" on top of "Blog" so that both sections take up the full width of the parent's content container. On desktop, "Degrees" and "Blog" again appear below "Events," but take up two-thirds of the parent container's width here; on 4K screens, the two sections appear in their own column (with

On mobile and tablet, the container for all the content on the page takes up the width of the page apart from 50px of padding on both the left and right. It is 950px wide and is centered on laptops and desktops less than 4K and is 2000px wide on desktops wider than 4K.

On mobile and tablet, both the main navigation links and search bar are replaced by a hamburger menu that can be clicked on to display a dropdown menu that shows the links and search bar laid out vertically (i.e., one on top of the next). On larger screens, the search bar always appears 300px wide and up against the right-hand side of the page's content container (fixed 50px below the top of the page), and the links in the middle always appear 274px wide and equally spaced between the "Brown CS" site header to the left and the search bar to the right.

On mobile and tablet, the "Events" section appears below "News" and above "Degrees" and "Blog" so that each section takes up the full width of the page's content container. On screens smaller than 4K, "Events" takes up two-thirds of the content container's width and appears alongside "News" and above "Degrees" and "Blog"; on 4K screens, the "Events" section takes up only one-third of the page's content container, appearing between a column for "News" and a column where "Degrees" appears above "Blog."

On all screens smaller than 4K, the two equally-sized square images for the lead event in the "Events" section appear alongside one another in a row. On 4K screens (where the "Events" column is made to take up its own column spanning a third of the width of the page's content container), the images become oriented vertically so that the image to the left appears above the image to the right.

On mobile, the three columns in the footer appear one on top of the other and flush against the left-hand side of the content container (i.e., the leftmost column appears 50px above the middle column, which appears 50px above the red "Sign In" text). On larger screens, the first of these columns always appears flush against the left-hand side of the content container while the other two columns appear in the rightmost third of the content container, with the five white links up against the left-hand side of this third and the red "Sign In" link up against the right-hand side of this third.

