

Aquatics - DIV Scoring Manager

ISS i-Judge Scoring Consoles

Included with the DIV Scoring Manager software is the ISS i-Judge Scoring Console Interface.

Connect up to 11 Windows based computers or tablets to the DIV Run Event software and your judges can enter their scores electronically directly into Run Event.

Requirements

- Windows 7, 8 or 10.
- Minimum screen resolution of 800x600. Auto sizes to fit your screen.
- 1 GHz processor.
- 4 GB Ram.
- 20 GB Hard Drive.
- Wireless network card.

The landscape orientation interface displays a header with event details: Round 1, Womens 3M Open Prelim, IND, 4 MICHELLE HEIMBERG SUI, 100 %, 405B DD: 3.0 3M Inward 2 1/2 Somersaults. The main area features a numeric keypad (0-9, Clear, 10) and a large score display showing 6.5. A 'Send (Enter)' button is located below the score. The judge's ID 'J: 5' is shown in a blue box at the bottom right. A status bar at the very bottom shows individual scores and the software version.


Landscape Orientation

The portrait orientation interface displays the same header information as the landscape view. The numeric keypad and score display (6.5) are arranged vertically. The 'Send (Enter)' button and the judge's ID 'J: 5' are also visible. The status bar at the bottom shows individual scores and the software version.


Portrait Orientation

User Manual

1. Install the latest version of i-Judge software on your Windows based computers or tablets.
2. Connect your Run Event computer to a network.
3. Connect your i-Judge consoles to the network. One i-Judge console for each judge.
4. Open an event in Run Event.
5. From the i-Judge menu in Run Event, choose **Connections Activity**.



6. From the Console Connections/Activity window, make a note of the IP Address.
7. Connect Consoles. You will see that ISS MMS is connected right away. This is Run Event.
Troubleshooting: If Connect Consoles fails, try another network. Something is blocking the TCP Port 8963.
8. From each console, run the i-Judge program.
9. Choose the IP address that corresponds to the Run Event computer.



*Note: If you are just testing, you can run i-Judge on the same computer as Run Event. To connect, choose **This Computer**.*

10. Select the judge assignment for the i-judge console.
11. Press Connect.
12. From Run Event, click on any diver. The information will display on all i-Judge consoles.
13. Enter the score for the dive from the i-Judge console.
Hint: Since diving scores to the ½ point, you can double click a number and the system will convert it to 0.5 (ex: 77 → 7.5).
14. Press **Send** followed by the **Accept / Send** buttons.
15. When all scores are received, press OK(enter) from Run Event to accept the scores.

Additional Information:

- If a console gets disconnected from the network, it will automatically try to reconnect when a score is sent.
- The Connections/Activity window shows the status of all consoles including their power meter.
- You can disconnect an i-Judge from the Connections/Activity window.
- The i-Judge console displays the power meter at the top right.

i-Judge is a product of Integrated Sports Systems (ISS) Inc. and has been designed to work with the DIV Scoring Manager by Swiss Timing Ltd.