# How to Install fS Software Win 8.x

**USER GUIDE #02-W8** 




## How to Install fotoShout Windows 8.x

## Do Not Install fotoShout Without Reviewing This Guide First


#### Be sure to view "Tips" at bottom of guide


- Login into the Apple App store using your iPad or iPad mini, download & install fotoShout. (If you haven't already done so)
- 2. Go <a href="http://fotoshout.com/">http://fotoshout.com/</a> (Computers must be running Windows 7, Windows 8.x 64 bit operating system.
  - a. login to fotoShout at http://fotoshout.com/
  - b. At the top of page click on "**Download**." Save the zip file to your computer.
    - i. A dialog box may pop up after the download completes, usually in the lower left corner of your computer screen stating, "fotoShout Client\_1.3\_Zip is not commonly downloaded and could be dangerous." Click on the Down Triangle lcon next to the word "Discard" select "Keep."
  - c. Unzip file; (right click file, select "Extract All"). After extraction your will be viewing 2 files.
    - i. fotoshout \_1.3\_WIN64.exe
    - ii. IIS.bat file
  - d. This is **IMPORTANT**
    - i. Disable your Firewall, and Anti-virus during installation and setup. We have found some antivirus software cause issues **during** setup.
    - ii. <u>Right click</u> the **IIS.bat** file, a popup menu will open. Select "Run As Administrator." The file will install, follow the prompts, it takes a minute or two. When complete text within a Black Dialog box will display "Press Any Key To Continue"
  - e. Press the Windows Key plus R at the same time. Win+R"
    - i. Type in "Control Panel" click OK, The control Panel will open.
    - ii. Within Control Panel (Category View) Under the Programs title, Click on "Uninstall a program".
    - iii. Dialog box will open On left side of screen click on "Turn Windows Features On or Off".
    - iv. A dialog box will open. Put a check mark in the following boxes to turn on the features. (follow selections from photo below) If the features is already On (checked) leave it checked.
      - 1. Net frame work 3.5 Press the "+" symbol to open the entire tree, check all boxes
      - 2. Net frame work 4.5 Press the "+" symbol to open the entire tree, check all boxes
      - 3. Click "+" Internet Information Services, Click "+" on Web Management tool. Put Check mark in \_Net Flexibility, \_Net Flexibility 4.5, \_ASP Net 3.5, \_ASP Net 3.5, \_ISAPI Extensions, \_ISAPI Filters
      - 4. After making selections Click "OK"
      - 5. Windows will now install features. This can take a while, 5 minutes or more
      - 6. After features have installed, close dialog box





- f. After IIS software has been installed & Windows Features Turned On
  - i. Right Click the "fotoShout \_1.3WIN64.exe" file. Select "Run as Administrator" A dialog box will pop up "fotoShout client requires the following items to be installed on your computer." Click the Install button. (Be patient this can take a while. fotoShout is installing your database)
  - ii. When the text appears "Success," close the dialog box.
  - iii. Click finish when the fotoShout dialog box when it pops up.
  - iv. Reboot Computer
- g. This portion of setup is unique to fotoShout **Beta**, and needs to be completed <u>only once</u> on each event computer.
  - i. Go to Windows Explorer. Type in "%programdata%\fotoshout" (without the quotes) press enter on the keyboard. Open the "SyncSettings.config" file (see images below) When Clicking on "Syncsettings.config" if you have Never viewed this type of file before, Windows will ask you what program you would like to use to read this file. Right Click on "syncsettings.config," Click on "More Options". Select and click on "Notepad". Syncsettings.config will now open.

- ii. Scroll down to **password** and **user name**. Replace the entered e-mail address with your username (**registered e-mail address**). Replace the word password with your actual "**password**."
- iii. Click on File, then Click "SAVE"
- iv. Go to Windows Explorer, type in- "%windir%\system32\services.msc" (without the quotes) press enter. A dialog box will open. Scroll down to "fotoShout Sync Service." Left click on "fotoShout Sync Service" to highlight. Click Start the Service. (see images below) Please note; Part of the message in the highlighted area will display "Started" and "Automatic," but you still need to click "Start Service" the very first time you install fotoShout.









### fotoShout software setup is complete



## **TIPS**

When installing a program in Windows 8.x be sure and Right Click program and select "Run as Administrator". Depending on your settings a Windows dialog box may pop up with text, such as, "Windows smart screen prevented an unrecognized app from starting, running this app might put you PC at risk". Do not click on the "OK" button, Click on the text "More Info." Then Click on "Run Anyway"

When Clicking on "Syncsettings.config" if you have **Never** viewed this type of file before, Windows will ask you what program you would like to use to read this file. Right Click on "syncsettings.config," Click on "**More Options**". Select and click on "**Notepad**". **Syncsettings.config** will now open.