How to Install fS Software

USER GUIDE #02



How to Install fotoShout (prerelease)

Do Not Install fotoShout Without Reviewing This Guide First

- 1. Login into the Apple App store using your iPad or iPad mini, download & install fotoShout. (If you haven't already done so)
- 2. Go http://fotoshout.com/ (Computers must be running Windows 7, Windows 8 or 8.1 64 bit operating system.
 - a. login to fotoShout at http://fotoshout.com/
 - b. At the top of page click on "**Download**." Save the zip file to your computer.
 - i. A dialog box may pop up after the download completes, usually in the lower left corner of your computer screen stating, "fotoShout Client_1.3_Zip is not commonly downloaded and could be dangerous." Click on the Down Triangle lcon next to the word "Discard" select "Keep." Click "Keep."
 - c. Unzip file; (right click file, select "Extract All"). After extraction your will be viewing 2 files.
 - i. fotoshout 1.3 WIN64.exe
 - ii. IIS.bat file

d. This is **IMPORTANT** -

- i. Disable your Firewall, and Anti-virus during installation and setup. We have found some antivirus software cause issues **during** setup.
- ii. <u>Right click</u> the **IIS.bat** file, a popup menu will open. Select "Run As Administrator." The file will install, follow the prompts, it takes a minute or two. When complete text within a Black Dialog box will display "Press Any Key To Continue"
- iii. After IIS is installed Right Click the "fotoShout _1.3WIN64.exe" file. Select "Run as Administrator" A dialog box will pop up "fotoShout client requires the following items to be installed on your computer." Click the Install button. (Be patient this can take a while. fotoShout is installing your database)
- iv. When the text appears "Success," close the dialog box.
- v. Reboot Computer
- e. This portion of setup is unique to fotoShout **Beta**, and needs to be completed <u>only once</u> on each event computer.
 - Go to Windows Explorer. Type in "%programdata%\fotoshout" (without the quotes)
 press enter on the keyboard. Open the "SyncSettings.config" file (see images
 below)
 - ii. Scroll down to password and user name. Replace the entered e-mail address with your e-mail address. Replace the word password with your actual "password."
 - iii. Go to Windows Explorer, type in- "%windir%\system32\services.msc" (without the quotes) press enter. A dialog box will open. Scroll down to "fotoShout Sync Service." Left click on "fotoShout Sync Service" to highlight. Click Start the Service. (see images below) Please note; Part of the message in the highlighted area will display "Started" and "Automatic," but you still need to click "Start Service" the very first time you install fotoShout.









