🚧 Emacs support for the Smalltalk Programming Language 🚧

Description	Keystroke	Function	Note
Smalltalk Editing <u>Last updated on:</u>	PEL supports for the Smalltalk programming language is experimental and not yet documented except for what you see here. 📦 The GNU **smalltalk-mode** external package is installed when 🖼 the **pel-use-smalltalk** user-option is set to t. 🚧 PEL supports GNU Smalltalk smalltalk-mode. This is minimal early support. 2025-04-26		
Open this PDF file. See also: 🖼 **Help/Info**	`<f11> SPC : <f1>` `<f12> <f1>`	(**pel-help-pdf** &optional OPEN-WEB-PAGE)	Open the **PL - Swift** local PDF. If the prefix argument (like **C-u** or **M--**) is used, then it opens the remote GitHub hosted raw PDF instead. If the **pel-flip-help-pdf-arg** user-option is set it's the other way around.
🖼 **Customize** PEL Swift support	`<f11> SPC : <f2>` `<f12> <f2>`	(**pel-customize-pel** &optional OTHER-WINDOW)	Customize PEL Swift support. • If OTHER-WINDOW is non-nil (use **C-u**), display in another window.
🖼 **Customize** Emacs Swift support	`<f11> SPC : <f3>` `<f12> <f3>`	(**pel-customize-library** &optional OTHER-WINDOW)	Customize Emacs Swift support: swift • If OTHER-WINDOW is non-nil (use **C-u**), display in another window.
Comments			
Toggle display of comments in buffer or active region See also: 🖼 **Comments**	`<f11> ; ;`	(**hide/show-comments-toggle** &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer. • If the region is active then toggle in the region. Otherwise, in the whole buffer. 📦 This requires the **hide-comnt.el** package (see 🖼 **Comments**). 🖼 PEL activates it when the **pel-use-hide-comnt** user option is **t**.

Emacs & Smalltalk — References

Document	Notes
The Smalltalk Programming Language	• Smalltalk @ Wikipedia • GNU Smalltalk @ Wikipedia • GNU Smalltalk home • GNU Smalltalk User Manual • GNU Smalltalk Library Reference • GNU Smalltalk Library Reference 2
Emacs support:	• **smalltalk-mode**