Emacs support for OCaml

| Description | <u>Keystroke</u> | Function | Note | |
|--|---|--|---|--|
| OCaml Editing | Emacs does not provide any built-in mode for OCaml. To activate support for OCaml on PEL, the pel-use-ocaml user-option must be turned on (set to t). | | | |
| See: OCaml Mode Manual | When pel-use-ocaml In a OCaml buffer thes the PEL pel-tuareg-ad | nade available. key. It also activates the ability to activate minor modes for the OCaml major mode through | | |
| | PEL provides the following user-options to download and activate OCaml supporting Emacs packages. It uses the tuareg-mode as the major mode for OCaml files. The <u>tuareg</u> external package is required. PEL installs and activates it when the <u>pel-use-tuareg</u> user-options is turned on. | | | |
| | The <u>tuareg</u> external package is required. PEL installs and activates it when the pel-use-tuareg user-options is turned on. The <u>caml-mode</u> external package is required. PEL installs and activates it when the pel-use-caml-mode user-options is turned on. | | | |
| | The <u>merlin</u> external package is required. 2 PEL installs and activates it when the pel-use-merlin user-options is turned on. | | | |
| | The Internal external package is required. The installs and activates it when the per-use-mentil user-options is turned on. | | | |
| | PEL support for OCaml is not complete. More commands should be provided and documented. OCaml support is preliminary. | | | |
| Open this PDF file. See also: <u>∑ Help/</u> Info | <f11> SPC o <f1></f1></f11> | (pel-help-pdf &optional OPEN-WEB-PAGE) | Open the <u>Nt - OCaml</u> local PDF. If the prefix argument (like C-u or M) is used, then it opens the remote GitHub hosted raw PDF instead. If the pel-flip-help-pdf-arg user-option is set it's the other way around. | |
| | <f12> <f1></f1></f12> | | | |
| ∑ Customize PEL OCaml support | <f11> SPC o <f2></f2></f11> | (pel-customize-pel &optional OTHER-WINDOW) | Customize PEL OCaml support. • If OTHER-WINDOW is non-nil (use C-u), display in another window. | |
| | <f12> <f2></f2></f12> | Will be with | | |
| ∑ Customize Emacs OCaml support | <f11> SPC o <f3></f3></f11> | (pel-customize-library &optional | Customize Emacs OCaml support: merlin, tuareg, tuareg-opam. • If OTHER-WINDOW is non-nil (use C - u), display in another window. | |
| | <f12> <f3></f3></f12> | OTHER-WINDOW) | | |
| Comments | | | | |
| Toggle display of comments in buffer or active region See also: ∑ Comments | <f11> ; ;</f11> | (hide/show-comments-toggle &optional START END) | Toggle hiding/showing of comments in the active region or whole buffer. • If the region is active then toggle in the region. Otherwise, in the whole buffer. • This requires the hide-comnt.el package (see December Comments). • PEL activates it when the pel-use-hide-comnt user option is t. | |
| | | | | |
| | | | | |
| | | | | |
| | | | | |

Emacs & OCaml — References

| Document | Notes |
|----------|-------|
| | |
| | |
| | |
| | |
| | |
| | |