🚧 Emacs support for Perl 🚧

Description	Keystroke	Function	Note

Perl Editing
 	
• ∑ **Indentation** control ☞
	Emacs provides the built-in perl-mode to support Perl programming. 🚧 PEL support for Perl is very preliminary; it mostly uses the built-in Perl support.
	
	PEL activates Perl support with the 🔲 **pel-use-perl** user-options. When it is turned on the **`<f11> SPC U`** prefix is made available. In a perl buffer these commands are accessible via the **`<f12>`** key. It also activates the ability to activate minor modes for the perl major mode through the PEL **pel-perl-activates-minor-modes** user-option.
	
	🔡 Perl indentation is controlled by the following user-options:
	• **perl-indent-level** sets the number of columns used for indentation. It defaults to 4.
	  • PEL sets **tab-width** with the same value in rust buffers so that manual indentation commands use the same number of columns to indent.
	• **pel-perl-use-tabs** controls whether hard tabs are used for indentation (nil by default).
	  • PEL sets **indent-tabs-mode** with the value of **pel-perl-use-tabs** in perl buffers.		

Open this PDF file. See also: ∑ **Help/ Info**	**`<f11> SPC P <f1>`** **`<f12> <f1>`**	(**pel-help-pdf** &optional OPEN-WEB-PAGE)	Open the 🔲 **- Perl** local PDF. If the prefix argument (like **`C-u`** or **`M--`**) is used, then it opens the remote GitHub hosted raw PDF instead. If the **pel-flip-help-pdf-arg** user-option is set it's the other way around.
∑ **Customize** PEL Perl support	**`<f11> SPC P <f2>`** **`<f12> <f2>`**	(**pel-customize-pel** &optional OTHER-WINDOW)	Customize PEL Perl support. • If OTHER-WINDOW is non-nil (use **`C-u`**), display in another window.
∑ **Customize** Emacs Perl support	**`<f11> SPC P <f3>`** **`<f12> <f3>`**	(**pel-customize-library** &optional OTHER-WINDOW)	Customize Emacs Perl support: perl. • If OTHER-WINDOW is non-nil (use **`C-u`**), display in another window.
Comments			
Toggle display of comments in buffer or active region See also: ∑ **Comments**	**`<f11> ; ;`**	(**hide/show-comments-toggle** &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer. • If the region is active then toggle in the region. Otherwise, in the whole buffer. 📦 This requires the **hide-comnt.el** package (see ∑ **Comments**). 🔲 PEL activates it when the **pel-use-hide-comnt** user option is **t**.

Emacs & Perl — References

Document	Notes