Move Cursor to...

Move to	char	line	current line in window	word	word	sentence	paragraph	page	screen	sexp	function	inner list	buffer	window
beginning/top		C-a	M-0 C-I							C-M-b			• M-< • <home></home>	
first non-whitespace in line	M-m													
back/previous/left	C-b	С-р		M-b	M- <right></right>	М-а	M-{	C-x [M-v	С-М-р	C-M-a	C-M- <up></up>		S-<left></left><f11> <left></left></f11>
forward/next/right	C-f	C-n		M-f	M- <left></left>	М-е	M-}	C-x]	C-v	C-M-n	С-М-е	C-M- <down></down>		S-right<f11> <right></right></f11>
center			C-I											
end/bottom		С-е	M C-I							C-M-f			• M-> • <end></end>	
ир														S-<up></up><f11> <up></up></f11>
down														S-<down></down><f11> <down></down></f11>
Middle-top-bottom	M-r													

Navigation/Editing based on Syntactic Units

Prefix/ key	Syntactic Unit	Move point	Killing/Deleting	Transpose
C-	character	C-f: (forward-char &optional N)		(transpose-chars ARG)
C-	character	C-b: (backward-char &optional N)		
C-	line	C-a:1. Text: (move-beginning-of-line ARG)2. Org-Mode: (org-beginning-of-line &optional N)		
C-	line	C-e:1. Text: (move-end-of-line ARG)2. Org-Mode: (org-end-of-line &optional N)		
M-	line	M-m: (back-to-indentation)		
C-	word	C- <right>: (pel-forward-token-start &optional N)</right>		
C-	word	C- <left>: (pel-backward-token-start &optional N)</left>		
M-	word	M-f: (forward-word &optional N) M- <right></right>		(transpose-words ARG)
M-	word	M-b: (backward-word &optional N) M- <left> M-Y</left>		
C-x C-	line			C-x C-t: (transpose-lines ARG)
C-M-	S-expression			(transpose-sexps ARG)

Prefix/ key	Syntactic Unit	Move point	Killing/Deleting		Transpose			
	paragraph		References					
	sentence		Hererenoes					
	1	Topic & Link		Description				
How to s	scroll line by lin	e in GNU Emacs?		M-0 C-I (Meta-zero Control-L) moves the line to the top of the window. Note that doing C-I several time will do the same thing (toggle from center, top, bottom)ß				
Emacs n	nove around sp	lit windows in a specified direction?	Describes the wi	Describes the wind move.el module				
moving t	to previous win	dow in emacs @ SuperUser						
Smart he	ome in Emacs							
How to r SuperUs		o to beginning of line instead of beginning of buffer?	@					
Jump to	first non-white	space character in line in emacs						
How to s	skip forward to	first whitespace character?						
With em	acs, how to go	to the pairing (balancing) parentheses						
	nake the curre + L in R console	nt prompt of R at the top of buffer in ESS just like						
	acs Manual - 5 number?	.5 How do I make Emacs display the current line (or						