↖ Topic Index

🚧 Emacs support for the V Programming Language 🚧

Description	Keystroke	Function	Note
V Editing	Emacs does not provide any built-in mode for the **V Programming Language**. To activate support for V on PEL, the **pel-use-v** user-option must be turned on (set to **t**). • When **pel-use-v is** turned on the **<f11> SPC n** prefix is made available. PEL provides the following user-options to download and activate V supporting Emacs packages. 📦 The **v-mode** external package is required. PEL installs and activates it when the **pel-use-v** user-options is set to **v-mode**. • You can also set it to vlang-mode to use an experimental and incomplete implementation currently supported by PEL. 🚧 PEL support for V is not complete. More commands should be provided and documented. V support is preliminary. ⚠️ The V programming language uses the **.v** file extension. The **Verilog hardware description language** uses the same file extension! • Emacs supports Verilog natively. • With the current PEL implementation, the activation of the V programming language via the **pel-use-v** user-option overrides supports for Verilog. • If you want support for Verilog you must currently turn support for V off by setting **pel-use-v** off (nil)		
Open this PDF file. See also: **∑ Help/ Info**	**<f11> SPC v <f1>** **<f12> <f1>**	(**pel-help-pdf** &optional OPEN-WEB-PAGE)	Open the **𝔓𝔈 - V** local PDF. If the prefix argument (like **C-u** or **M--**) is used, then it opens the remote GitHub hosted raw PDF instead. If the **pel-flip-help-pdf-arg** user-option is set it's the other way around.
∑ Customize PEL V support	**<f11> SPC v <f2>** **<f12> <f2>**	(**pel-customize-pel** &optional OTHER-WINDOW)	Customize PEL V support. • If OTHER-WINDOW is non-nil (use **C-u**), display in another window.
∑ Customize Emacs V support	**<f11> SPC v <f3>** **<f12> <f3>**	(**pel-customize-library** &optional OTHER-WINDOW)	Customize Emacs V support: v • If OTHER-WINDOW is non-nil (use **C-u**), display in another window.
Comments			
Toggle display of comments in buffer or active region See also: **∑ Comments**	**<f11> ; ;**	(**hide/show-comments-toggle** &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer. • If the region is active then toggle in the region. Otherwise, in the whole buffer. 📦 This requires the **hide-comnt.el** package (see **∑ Comments**). PEL activates it when the **pel-use-hide-comnt** user option is **t**.

Emacs & V — References

Document	Notes
The V Programming Language	• V home page • V @ GitHub
V is under development	V is still under development. It seems to be an interesting project with impressive goals. It will be interesting to see where this project goes, as it has several detractors (but is there any one language/implementation everyone loves?)
Emacs support: v-mode @ GitHub	