Emacs support for OCaml

Description	<u>Keystroke</u>	Function	<u>Note</u>	
OCaml Editing	Emacs does not provide any built-in mode for OCaml. To activate support for OCaml on PEL, the pel-use-ocaml user-option must be turned on (set to t).			
See: OCaml Mode Manual	 When pel-use-ocaml is turned on the <f11> SPC o prefix is made available.</f11> In a OCaml buffer these commands are accessible via the <f12> key. It also activates the ability to activate minor modes for the OCaml major mode through the PEL pel-tuareg-activates-minor-modes user-option.</f12> 			
	PEL provides the following user-options to download and activate OCaml supporting Emacs packages. It uses the tuareg-mode as the major mode for OCaml files. This requires the following other external packages:			
	The <u>tuareg</u> external package is required. BEL installs and activates it when the pel-use-tuareg or pel-use-ocaml user-options is turned on.			
	The caml-mode external package is required. PEL installs and activates it when the pel-use-caml-mode or pel-use-ocaml user-options is turned on.			
	The merlin external package is required. PEL installs and activates it when the pel-use-merlin or pel-use-ocaml user-options is turned on.			
	PEL support for OCaml is not complete. More commands should be provided and documented. OCaml support is preliminary.			
Last updated on:	2025-05-17			
Open this PDF file. See also: <u>Neelp/</u> Info	<f11> SPC o <f1></f1></f11>	(pel-help-pdf &optional OPEN-WEB- PAGE)	Open the NL - OCaml local PDF. If the prefix argument (like C-u or M) is used, then it opens the remote GitHub hosted raw PDF instead. If the pel-flip-help-pdf-arg user-option is set it's the other way around.	
	<f12> <f1></f1></f12>			
© Customize PEL OCaml support	<f11> SPC o <f2></f2></f11>	(pel-customize-pel &optional OTHER-	Customize PEL OCaml support. • If OTHER-WINDOW is non-nil (use C - u), display in another window.	
	<f12> <f2></f2></f12>	WINDOW)		
© Customize Emacs OCaml support	<f11> SPC o <f3></f3></f11>	(pel-customize-library &optional OTHER-WINDOW)	Customize Emacs OCaml support: merlin, tuareg, tuareg-opam. • If OTHER-WINDOW is non-nil (use C-u), display in another window.	
	<f12> <f3></f3></f12>			
Comments				
Toggle display of comments in buffer or active region See also: Comments	<f11> ; ;</f11>	(hide/show-comments-toggle &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer. • If the region is active then toggle in the region. Otherwise, in the whole buffer. • This requires the <a doi.org="" href="https://doi.org/li> This requires the <a doi.org="" href="https://doi.org/li> <a <="" href="https://doi.org/li> 	

Emacs & OCaml — References

Document	Notes
Information about OCaml	OCaml @ Wikipedia OCaml home