

Emacs Support for GNU Guile🚧

Description	Keystroke	Function	Note
GNU Guile Programming Language Support See also: • Guile Reference Manual • File/Directory Variables Last updated on: 2026-09-19	 PEL support for Guile Scheme is preliminary. More work is required to identify Guile specific support.  PEL activates Guile Scheme support when the pel-use-guile user-option is turned on (t). PEL provide extra support for the Guile programming language. Most support is provided by Emacs support for pel - Scheme . • The Guile programming language is a Scheme implementation. The Guile Scheme files use the same extension as Scheme: .ss.		
Open this PDF file. See also: Help/Info	<f11> SPC C-s C-g <f1> <f12> <f1>	(pel-help-pdf &optional OPEN-WEB-PAGE)	Open the pel - GNU Guile local PDF. With C-u , M-- , M- -1 or C- -1 prefix: open the remote GitHub hosted PDF instead. If the pel-flip-help-pdf-arg user-option is set it's the other way around.
Customize PEL Guile support	<f11> SPC C-s C-g <f2> <f12> <f2>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL Guile support. • If OTHER-WINDOW is non-nil (use C-u), display in another window.
Customize Emacs Guile support	<f11> SPC C-s C-g <f3> <f12> <f3>	(pel-customize-library &optional OTHER-WINDOW)	Customize Emacs Scheme support: scheme, geiser, quack, lispy. • If OTHER-WINDOW is non-nil (use C-u), display in another window.
Use the following commands to interact with the gsi Scheme Guile REPL			
Open the Guile REPL	<f11> z r C-g <f12> z	(pel-guile-repl &optional N)	Run the Guile REPL in window specified by N. • By default use the other window. If a numeric argument is specified, its value correspond to the direction of a numeric keypad: 8 4 6 2 That is: • 8: up • 4: left • 6: right • 2: down • 0 and 5 identify the current window.
Erase the content of REPL	<f12> C-l	(pel-clear-scheme-repl-buffer)	Erase content of the Guile REPL running under Emacs.