

⚠️

Emacs support for OCaml

⚠️

Description	Keystroke	Function	Note
OCaml Editing See: OCaml Mode Manual Last updated on:	Emacs does not provide any built-in mode for OCaml.  To activate support for OCaml on PEL, the pel-use-ocaml user-option must be turned on (set to t). - When pel-use-ocaml is turned on the <f11> SPC o prefix is made available. - In a OCaml buffer these commands are accessible via the <f12> key. It also activates the ability to activate minor modes for the OCaml major mode through the PEL pel-tuareg-activates-minor-modes user-option. PEL provides the following user-options to download and activate OCaml supporting Emacs packages. It uses the tuareg-mode as the major mode for OCaml files. This requires the following other external packages:  The tuareg external package is required.  PEL installs and activates it when the pel-use-tuareg or pel-use-ocaml user-options is turned on.  The caml-mode external package is required.  PEL installs and activates it when the pel-use-caml-mode or pel-use-ocaml user-options is turned on.  The merlin external package is required.  PEL installs and activates it when the pel-use-merlin or pel-use-ocaml user-options is turned on.  PEL support for OCaml is not complete. More commands should be provided and documented. OCaml support is preliminary. 2026-09-19		
Open this PDF file. See also: 📖 Help/Info	<f11> SPC o <f1> <f12> <f1>	(pel-help-pdf &optional OPEN-WEB-PAGE)	Open the  - OCaml local PDF. With C-u , M-- , M- -1 or C- -1 prefix: open the remote GitHub hosted PDF instead. If the pel-flip-help-pdf-arg user-option is set it's the other way around.
📖 Customize PEL OCaml support	<f11> SPC o <f2> <f12> <f2>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL OCaml support. If OTHER-WINDOW is non-nil (use C-u), display in another window.
📖 Customize Emacs OCaml support	<f11> SPC o <f3> <f12> <f3>	(pel-customize-library &optional OTHER-WINDOW)	Customize Emacs OCaml support: merlin, tuareg, tuareg-opam. If OTHER-WINDOW is non-nil (use C-u), display in another window.
Comments			
Toggle display of comments in buffer or active region See also: 📖 Comments	<f11> ; ;	(hide/show-comments-toggle &optional START END)	Toggle hiding/showing of comments in the active region or whole buffer. If the region is active then toggle in the region. Otherwise, in the whole buffer.  This requires the hide-comnt.el package (see 📖 Comments).  PEL activates it when the pel-use-hide-comnt user option is t.

Emacs & OCaml — References

Document	Notes
Information about OCaml	OCaml @ Wikipedia OCaml home