

Editing SSH Configuration Files

Description	Keystroke	Function	Note
Editing SSH Configuration files with Emacs See also:  ssh for info on SSH itself. Last updated on: 2026-09-20	Emacs does not provide any specific major modes for editing SSH configuration files, but some external packages do. PEL supports the following external package:  The external package emacs-ssh-files-mode provides major modes that highlight the hostname and key protocol in the SSH authorized_keys and known_host. It provides 2 major modes: ssh-authorized-keys-mode and ssh-known-hosts-mode for the ssh authorized_keys and known_hosts files. When  pel-use-emacs-ssh-file-modes is on, PEL installs and uses my fork of this project (until my PR and other I wrote get merged).		
Open this PDF file. See also:  Help/Info	<f11> SPC 0 <f1> <f11> SPC 1 <f1>	(pel-help-pdf &optional OPEN-WEB-PAGE)	Open the SSH files local PDF. With C-u , M-- , M- -1 or C- -1 prefix: open the remote GitHub hosted PDF instead. If the pel-flip-help-pdf-arg user-option is set it's the other way around.
	<f12> <f1>		
 Customize PEL ssh-file-modes support	<f11> SPC 0 <f2> <f11> SPC 1 <f2>	(pel-customize-pel &optional OTHER-WINDOW)	Customize PEL ssh-file-modes support. If the prefix argument is non-nil (like C-u or M--) , display in other window.
	<f12> <f2>		
 Customize ssh-file-modes	<f11> SPC 0 <f3> <f11> SPC 1 <f3>	(pel-customize-library &optional OTHER-WINDOW)	Customize the ssh-files-mode If the prefix argument is non-nil (like C-u or M--) , display in other window.
	<f12> <f2>		
Toggle SSH Abbreviated Keys Mode	<f12> =	(ssh-abbreviated-keys-mode &optional ARG)	This is a minor mode. If called interactively, toggle the 'ssh-abbreviated-keys-mode'. - If the prefix argument is positive, enable the mode, and if it is zero or negative, disable the mode. - If called from Lisp, toggle the mode if ARG is 'toggle'. Enable the mode if ARG is nil, omitted, or is a positive number. Disable the mode if ARG is a negative number.  When the ssh-authorized-keys-mode and ssh-known-hosts-mode are activated the ssh abbreviated keys minor mode is automatically activated if the ssh-abbreviated-mode-default user-option is turned on (set to t).