


30/08/2026

Assignment-3

Created By
~Pintu Mer

1. Log in to your home **Wi-Fi** router's admin panel using its default **IP** address (usually **192.168.0.1** or **192.168.1.1**) and take a screenshot of the login page. Hint: If you don't know your router's IP, open **Command Prompt** and run '**ipconfig**' — look for '**Default Gateway**'.



2. Find and note down the current **IP** address, subnet mask, and default gateway assigned to your laptop or mobile device when connected to your **Wi-Fi** network.

IPv4 Address : 192.168.1.97

Subnet Mask : 255.255.255.0

Default Gateway : 192.168.1.4

3. Change your device's **IP** address from '**Obtain IP automatically**' (**DHCP**) to a static **IP** in the same range as your router (for example, set it to **192.168.1.50** if your router is **192.168.1.1**), and test if you still have internet access. Remember to revert to automatic/**DHCP** after testing to avoid network issues.

Steps:

1. Open **Settings** → **Network & Internet** → **Wi-Fi**.
2. Select your connected **Wi-Fi** network.
3. Open **IP Assignment** → **Edit**.
4. Change **Automatic (DHCP)** to **Manual**.
5. Turn **IPv4 ON**.

6. Enter:

- **IP Address: 192.168.1.50**
- **Subnet Prefix Length: 24**
- **Gateway: 192.168.1.1**
- **Preferred DNS: 8.8.8.8**
- **Alternate DNS: 1.1.1.1**

7. Click Save.

8. Open a website and check the Internet connection.

9. After testing, change Manual back to Automatic (DHCP).

Result:

The device was successfully configured with a static IP address, and the Internet connection was tested. After testing, the IP setting was restored to DHCP.

- 4. In your router's admin panel, locate the section where you can view or change the DHCP range. Write down the current range, and explain in 2-3 lines what would happen if two devices are assigned the same IP address in this range.**

Step 1: Open Router Admin Panel

Open a browser and enter your router's IP address, for example:
192.168.1.1

Step 2: Login

Enter your **router username and password** to open the admin panel.

Step 3: Open DHCP Settings

Go to **Network / LAN Settings → DHCP Settings**.

Step 4: Check DHCP Range

Find the **DHCP Start IP** and **DHCP End IP**.

Example:

192.168.1.100 - 192.168.1.200

Step 5: Write the Current Range

Current DHCP Range: 192.168.1.100 - 192.168.1.200

Step 6: What happens if two devices get the same IP?

If two devices have the same IP address, an **IP conflict** occurs.

Both devices may have **connection problems or may not be able to access the network/internet properly**.