


12/8/2026

Assignment-4

Created By
~pintu mer

1. Connect a USB webcam to your computer, install any required drivers, and verify that the webcam works by opening the default camera app and capturing a photo



❖ Steps – USB Webcam

1. Connect – Plug the USB webcam into the computer.
2. Install Driver – Wait for Windows to install the driver.
3. Open Camera – Open the Camera app.
4. Check Video – Make sure your webcam video is visible.
5. Take Photo – Click the Camera button to capture a photo.
6. Check Photo – Open the saved photo from the Pictures folder.

2. Set up a local printer (USB or network), install the correct driver, and print a test page to confirm successful installation.



Set Up a Local Printer

1. **Connect the Printer**
 - Connect the printer to the computer using a **USB cable** or connect it to the same **Wi-Fi network**.
2. **Turn ON the Printer**
 - Make sure the printer is powered on and ready.
3. **Open Printer Settings**
 - Go to **Settings** → **Devices** → **Printers & scanners**.
4. **Add Printer**
 - Click **Add a printer or scanner** and select your printer.
5. **Install Driver**
 - Windows will install the correct **printer driver**. If needed, install the driver from the printer manufacturer's website.

6. Set as Default

– Select the printer and choose **Set as default**.


7. Print Test Page

– Open **Printer Properties** → **Print Test Page**.

8. Confirm

– If the test page prints correctly, the printer is **successfully installed**

3. Simulate a connectivity issue by unplugging the printer's USB cable, then use Windows Device Manager to identify and resolve the 'printer not detected' problem. Hint: Check for error icons and use the 'Scan for hardware changes' option after reconnecting.





Printer Not Detected – Troubleshooting Steps

1. Unplug USB Cable

- Disconnect the printer's USB cable from the PC.

2. Check Printer

- Windows may show that the printer is not detected.

3. Open Device Manager

- Right-click Start → Device Manager.

4. Check for Error Icon

- Look under Printers or Universal Serial Bus controllers for a yellow warning icon .

5. Reconnect USB Cable

- Plug the printer's USB cable back into the PC.

6. Scan for Hardware Changes

- In Device Manager, click Action → Scan for hardware changes.


7. Check Again

- Make sure the printer appears without a warning icon.

8. Test the Printer

- Open Printers & scanners and print a test page.

4. A user reports that their webcam video is not displaying in Zoom, but it works in the default camera app. Troubleshoot and resolve the issue so the webcam works in both applications. Hint: Check if another app is using the webcam or if Zoom permissions are enabled.



Webcam Not Working in Zoom – Simple Steps

1. **Test the Webcam** – Open the **Camera app** and check that the webcam works.

2. **Close Other Apps** – Close Camera, Teams, Skype, or any other app using the webcam.
3. **Open Zoom Settings** – Open **Zoom** → **Settings** → **Video**.
4. **Select Webcam** – Select the correct webcam from the **Camera** list.
5. **Check Camera Permission** – Go to **Windows Settings** → **Privacy** → **Camera** and turn **Camera access ON**.
6. **Allow Zoom** – Make sure **Allow desktop apps to access your camera** is ON.
7. **Restart Zoom** – Close Zoom completely and open it again.
8. **Test Video** – Start a Zoom test meeting and check that the webcam video is displayed.