
TechnobizTrader

Setup & Connection Guide

Multi-Agent ICT Trading System with GUI




Document version 1.0 · May 5, 2026

Liquidity Sweep · Break of Structure · Imbalance/Order Block · Pullback Entry

1. System Overview

TechnobizTrader is a multi-agent trading system that pairs an interactive office GUI (rendered in your browser) with a real Python backend running the ICT (Inner Circle Trading) pipeline. Click START CYCLE in the GUI and three specialist agents — Trend-Master, Analyse-Master, Trader-Master — execute one full cycle against live MT5 market data. Optional Telegram broadcast lets you push every validated signal to a channel, group, or DM.



2. Prerequisites

Before you start, make sure the following are in place:

- Python 3.10 or newer (Windows recommended for MT5 support).
- MetaTrader 5 desktop terminal installed, with valid broker credentials and the terminal logged in. Required only when you actually want to trade.
- (Optional) A Telegram bot — create one by chatting with @BotFather on Telegram, then add the bot to your channel or group as an admin.
- (Optional) The numeric Chat ID of the destination channel, group, or DM. For channels this is typically a negative number like -1001234567890.

What we'll build in 8 steps

Install dependencies → run the backend → open the browser → enter MT5 + Telegram credentials → spawn the 3 ICT agents → assign tasks → press START CYCLE → watch them walk through the office and log every trade in real time.

3. Install & Run

Steps 1 and 2 set up the backend. Run them once per machine.

1 Install dependencies

Open a terminal in the project folder, then run:

```
pip install -r requirements.txt
```

If your requirements.txt does not yet include the GUI dependencies, also run:

```
pip install fastapi uvicorn sse-starlette httpx python-dotenv reportlab
```

2 Start the backend server

From the same folder, launch:

```
python gui_server.py
```

On startup the server connects to MT5, builds the three trading agents, and begins listening on:

```
http://127.0.0.1:8765
```

If MT5 is not yet running, the server still starts — you'll be able to enter credentials in the GUI, and the connection will be retried automatically.

3 Open the GUI

Open the URL above in any modern browser.
The office floor will be empty at first.
The status panel (bottom-right) will read "Ready"
or briefly "Initializing services..." while it connects.

4. Connect MetaTrader 5

Click the gold ■ Settings button in the right sidebar of the GUI to open the credentials modal. Choose MetaTrader 5 from the Provider dropdown and fill in:

- Account Number — your MT5 login id, e.g. 12345678
- Password — your MT5 trading or investor password.
- Server — the broker server name shown in the MT5 terminal.

Click Save & Connect. The status panel will switch to Ready when the link is established.

■ Settings — Data Provider Credentials

Provider

MetaTrader 5

Account Number

12345678

Save & Connect

Server

BrokerName.Server

5. (Optional) Connect Telegram for signal broadcast

When Telegram is configured, every TradeSignal generated by the Analyse-Master is broadcast as a SIGNAL ALERT message — even if your Trader-Master later rejects the signal for risk-management reasons. Setup is the same modal, with Provider set to Telegram (signal broadcast).

- Bot Token — issued by @BotFather when you run /newbot. Paste it whole, e.g. 123456:ABC-DEF1234ghIkl-zyx57W2v1u123ew11.
- Chat ID — destination channel/group/DM id. Use a userinfo bot or call the Telegram API getUpdates to find yours.

Example broadcast — what subscribers receive:

■ SIGNAL ALERT ■

■ #XAUUSD

■ Trade Details: ■ #SELL

■ Entry Point: 4695

■ Stop Loss (SL): 4703

■ Take Profit 1 (TP1): 4692

■ Take Profit 2 (TP2): 4687

■ Take Profit 3 (TP3): 4679

■ Risk no more than 1-2% of your balance.

6. Add the three core agents


Click the +Agent toolbar button. In the modal, choose Role to spawn the matching core agent — each one walks into the Main Office (top-right) where they idle until tasked.

- ■ Trend-Master → goes to the Trend room when the cycle starts.
- ■ Analyse-Master → goes to the Analyse room.
- ■ Trader-Master → goes to the Trader room.


Pick any costume; the role is what assigns the office. While idle the agents will wander the Main Office, sit at the conference table, take coffee breaks in the kitchen, or use the restroom.

7. Assign tasks

Click Assign on the right sidebar. For each agent pick the recommended task (Analyze Market Trend / Detect ICT Patterns / Execute Trade) and click Assign Task. Once all three agents are tasked you're ready to run a cycle.

A rectangular button with a light orange background and a thin black border. It contains a small black square icon followed by the text "Trend-Master".

■ Trend-Master

A rectangular button with a medium blue background and a thin black border. It contains a small black square icon followed by the text "Analyse-Master".

■ Analyse-Master


A rectangular button with a medium blue background and a thin black border. It contains a small black square icon followed by the text "Trader-Master".

■ Trader-Master

8. Run a cycle

In the bottom toolbar, type the trading pair (e.g. EURUSD or XAUUSD) and click START CYCLE. The backend immediately runs the real ICT pipeline and the GUI mirrors each phase in real time:

- Trend-Master walks out of the Main Office, through the hallway, and into the Trend room. They sit, the door closes, and the arms-typing animation kicks in while the agent's analyze() method runs server-side.
- When the trend phase is complete the agent stands up, exits, and the baton passes to Analyse-Master, who repeats the routine.
- If the Analyse-Master generates a TradeSignal, the server immediately broadcasts a SIGNAL ALERT to Telegram (if configured).
- Trader-Master walks in last, evaluates risk, and either executes the trade via MT5 or rejects it. The status panel shows direction, RR, ticket id.



Each box's Server-Sent Event drives the on-screen agent to walk, sit, work, and exit.

9. Office layout map

The diagram below mirrors the GUI floor plan. Two narrow vertical hallways and one wide main hallway connect every room — agents always travel through doors, never through walls.



Pets wander the kitchen avoiding furniture. Restroom is single-occupancy (toilet lid opens & closes; agents wash hands at the sink).

10. Troubleshooting

If something does not behave as expected, walk through this list before anything else.

■ Backend not running

The browser shows "Service temporarily unavailable" or the status panel never leaves "Initializing services...". Restart the backend with: `python gui_server.py`.

■ MT5 not connected

The status panel says MT5 is not connected. Check that (a) the MT5 desktop terminal is open and logged in; (b) the credentials in Settings → MT5 match your broker; (c) Algo Trading is enabled in MT5 (the icon in the toolbar should be green).

■ No signal generated

Cycle finishes without a trade. This is normal — the Analyse-Master only emits a TradeSignal when ALL four ICT conditions (Sweep, BoS, Imbalance/OB, Pullback) are satisfied. Most cycles will not produce a signal.

■ Telegram not posting

Check the bot token (re-issue with `/token` in @BotFather if needed). Make sure the bot is added to the destination channel as an admin and that the chat id is correct.

■ Cycle fails immediately

Usually means one of the three core agents was not added before pressing START CYCLE. Use `+Agent` to spawn Trend-Master, Analyse-Master, and Trader-Master first.

Need a fresh start?

Stop the server (Ctrl+C), refresh the browser, then re-run `python gui_server.py`.

All credentials persist in `.env` so you only need to enter them once.