

Ex.No:10**Date:06/10/25**

CUSTOMIZE SWITCH WITH NETWORK MODULES USING CISCO PACKET TRACER

Aim:

To Customize Switch with Network Modules using Cisco Packet Tracer.

Procedure:

1. Open Cisco Packet Tracer

- Launch Cisco Packet Tracer on your computer.


2. Add a Switch to Your Workspace

- In the device toolbar (usually on the left side of the screen), locate the "Switches" section.
- Drag and drop a switch model onto the workspace.




3. Access the Switch's Physical Layout

- Click on the switch in the workspace to open its configuration window.
- Navigate to the "Physical" tab to see the switch's physical layout and modules.



4. Add Network Modules

- In the "Physical" tab, you might see options to add or modify network modules.
- Click on the slot where you want to add a module.
- Drag the module from the list of available modules and drop it into the slot on the switch.



5. Configure the Modules and save the configuration

- After adding the module, switch to the "CLI" tab in the switch's configuration window.
- Here, you can configure the ports provided by the module. For example, you can set IP addresses, VLAN configurations, and other settings for the new interfaces.

CONFIG THE HOSTNAME OF THE SWITCH:

```
Switch>enable
Switch#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#hostname CyberSwitch
CyberSwitch(config)#exit
CyberSwitch#
%SYS-5-CONFIG_I: Configured from console by console
```

SET THE MESSAGE OF THE DAY(MOTD) BANNER FOR THE SWITCH:

```
CyberSwitch#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
CyberSwitch(config)#banner ?
  motd  Set Message of the Day banner
CyberSwitch(config)#banner motd ?
  LINE  c banner-text c, where 'c' is a delimiting character
CyberSwitch(config)#banner motd $
Enter TEXT message. End with the character '$'.
##Unauthorized Access Is Prohibited##
$
```

CONFIG THE LINE CONSOLE PASSWORD AND ENABLE SECRET PASSWORD:

```
CyberSwitch(config)#line con 0
CyberSwitch(config-line)#password cisco
CyberSwitch(config-line)#login
CyberSwitch(config-line)#exit
CyberSwitch(config)#enable secret cisco123
CyberSwitch(config)#exit
CyberSwitch#
%SYS-5-CONFIG_I: Configured from console by console
```

```
##Unauthorized Access Is Prohibited##
```

```
User Access Verification
```

```
Password:
```

```
CyberSwitch>enable
```

```
Password:
```

```
Password:
```

```
CyberSwitch#
```

SHOW THE VLAN:

```
CyberSwitch#show vlan
```

VLAN	Name	Status	Ports
1	default	active	Fa0/1, Fa1/1, Fa2/1, Fa3/1 Fa4/1, Fa5/1, Fa6/1, Gig7/1 Fa8/1, Eth9/1
1002	fddi-default	active	
1003	token-ring-default	active	
1004	fddinet-default	active	
1005	trnet-default	active	

VLAN	Type	SAID	MTU	Parent	RingNo	BridgeNo	Stp	BrdgMode	Trans1	Trans2
1	enet	100001	1500	-	-	-	-	-	0	0
1002	fddi	101002	1500	-	-	-	-	-	0	0
1003	tr	101003	1500	-	-	-	-	-	0	0
1004	fdnet	101004	1500	-	-	-	ieee	-	0	0
1005	trnet	101005	1500	-	-	-	ibm	-	0	0

VLAN	Type	SAID	MTU	Parent	RingNo	BridgeNo	Stp	BrdgMode	Trans1	Trans2

```
Remote SPAN VLANs
```

Primary	Secondary	Type	Ports

```
CyberSwitch#
```

NAMING THE VLAN:

```
CyberSwitch#conf t
```

```
Enter configuration commands, one per line. End with CNTL/Z.
```

```
CyberSwitch(config)#vlan 10
```

```
CyberSwitch(config-vlan)#name sale
```

```
CyberSwitch(config-vlan)#exit
```

```
CyberSwitch(config)#
```

ASSIGN INTERFACE TO VLAN:

```
CyberSwitch(config)#interface FastEthernet3/1
CyberSwitch(config-if)#exit
CyberSwitch(config)#interface FastEthernet0/1
CyberSwitch(config-if)#switchport access vlan 10
CyberSwitch(config-if)#exit
CyberSwitch(config)#exit
CyberSwitch#
%SYS-5-CONFIG_I: Configured from console by console
```

ASSIGN IP ADDRESS TO VLAN

```
CyberSwitch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
CyberSwitch(config)#interface vlan 10
CyberSwitch(config-if)#
%LINK-5-CHANGED: Interface Vlan10, changed state to up

CyberSwitch(config-if)#ip address 192.168.10.1 255.255.255.0
CyberSwitch(config-if)#no shutdown
CyberSwitch(config-if)#exit
CyberSwitch(config)#exit
CyberSwitch#
%SYS-5-CONFIG_I: Configured from console by console

CyberSwitch#write memory
Building configuration...
[OK]
CyberSwitch#
```

Result:

Thus successfully configured and customize switch with network modules using cisco packet tracer has been verified.