LAb-2) determine IP address of the router and explore the ping command..




fig -1.1 Determine of IP address of the router

```
PC>ping 20.0.0.2

Pinging 20.0.0.2 with 32 bytes of data:

Reply from 20.0.0.2: bytes=32 time=0ms TTL=127

Ping statistics for 20.0.0.2:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 0ms, Average = 0ms
```

fig-1.2 determine IP address of the router and explore the ping command

sleps for router configration.

\* In end devices select 2 pc pco and pc2

\* go to the pco and click on fast Internet 0 ender I paddress 10.0.0.2 and

submission marks should be 250.0.0.0

submission marks should be 250.0.0.0.

submission marks should be 250.0.0.0.

both pco and pc1 will be different network

both pco and pc1 will be different network

similarly go to the router and click on con clI and write fellowing

command -> enable

command -> enable

interface last the ethernel 0/0

in address 10.0.0.2 255.0.0.0

## now write again 2 steps for routers (1) interface fastethernet 210. (D) ip address 20.0.0.1 255.0.0.0. (3) no suldown now go to the pco and lonting enter gate way 10.0.0.2 \* and go to the 2nd pc and config enter gateway 20.0.01 chulchy to wether epc connected ornot -> go to the pco and Destop and M'command prompt write ping - 20.0.0.2 observation. > ping 20.0.0.2 Pinging 20.0.0.2 with 32 bystes of Data: Peply from 20.0.0.2: bytes = 32 time oms TTL = 127 feply from 20.0.0.2 : bytes = 32 time OMS TIL= 12 } Reply from 20.0.0.2: bytes=32 time one TT L=127 feply from 20.0.0.2; bytes = 32 time OMS TIL= ping statistics for 20.0.0.2; Packet & sent: 4 recived= 04 lost=0 (01. loss) Approximate round trip name in Hilli - Seconds!

Minimum Foms, Haximum = oms Avarage = oms