




Press RETURN to get started.

Router>

Router>enable

Router#show ip interface brief

Interface	IP-Address	OK?	Method	Status	Protocol
Ethernet0/0	10.0.0.1	YES	manual	up	up
Ethernet0/1	20.0.0.1	YES	manual	up	up
Ethernet0/2	unassigned	YES	unset	administratively down	down
Ethernet0/3	unassigned	YES	unset	administratively down	down

Router#show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
 D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
 N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
 E1 - OSPF external type 1, E2 - OSPF external type 2
 i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
 ia - IS-IS inter area, * - candidate default, U - per-user static route
 o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
 a - application route
 + - replicated route, % - next hop override, p - overrides from PfR

Gateway of last resort is not set

```

      10.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
C       10.0.0.0/8 is directly connected, Ethernet0/0
L       10.0.0.1/32 is directly connected, Ethernet0/0
      20.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
C       20.0.0.0/8 is directly connected, Ethernet0/1
L       20.0.0.1/32 is directly connected, Ethernet0/1
S       30.0.0.0/8 [1/0] via 20.0.0.2
S       40.0.0.0/8 [1/0] via 20.0.0.2

```

Router#

```

R2
*Jul 15 10:59:51.860: %IP-4-DUPADDR: Duplicate address 30.0.0.1 on Ethernet0/1, sourced by aabb.cc00.0210
R2#
*Jul 15 11:00:21.860: %IP-4-DUPADDR: Duplicate address 30.0.0.1 on Ethernet0/1, sourced by aabb.cc00.0210
R2#
*Jul 15 11:00:51.860: %IP-4-DUPADDR: Duplicate address 30.0.0.1 on Ethernet0/1, sourced by aabb.cc00.0210
R2#
*Jul 15 11:01:21.860: %IP-4-DUPADDR: Duplicate address 30.0.0.1 on Ethernet0/1, sourced by aabb.cc00.0210
R2#
*Jul 15 11:01:51.860: %IP-4-DUPADDR: Duplicate address 30.0.0.1 on Ethernet0/1, sourced by aabb.cc00.0210
R2#
*Jul 15 11:02:21.860: %IP-4-DUPADDR: Duplicate address 30.0.0.1 on Ethernet0/1, sourced by aabb.cc00.0210
R2#
*Jul 15 11:02:51.860: %IP-4-DUPADDR: Duplicate address 30.0.0.1 on Ethernet0/1, sourced by aabb.cc00.0210
R2#
*Jul 15 11:03:21.860: %IP-4-DUPADDR: Duplicate address 30.0.0.1 on Ethernet0/1, sourced by aabb.cc00.0210
R2#show ip interface brief
Interface                IP-Address      OK? Method Status      Protocol
Ethernet0/0              20.0.0.2        YES manual up          up
Ethernet0/1              30.0.0.1        YES manual up          up
Ethernet0/2              unassigned      YES TFTP  down        down
Ethernet0/3              unassigned      YES TFTP  down        down
R2#show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2
       i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
       ia - IS-IS inter area, * - candidate default, U - per-user static route
       o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
       a - application route
       + - replicated route, % - next hop override, p - overrides from PFR

Gateway of last resort is not set

S    10.0.0.0/8 [1/0] via 20.0.0.1
    20.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
C    20.0.0.0/8 is directly connected, Ethernet0/0
L    20.0.0.2/32 is directly connected, Ethernet0/0
    30.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
C    30.0.0.0/8 is directly connected, Ethernet0/1
L    30.0.0.1/32 is directly connected, Ethernet0/1
S    40.0.0.0/8 [1/0] via 30.0.0.2
R2#

```

R3

```
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#interface ethernet 0/1
R3(config-if)#ip address 30.0.0.2 255.0.0.0
R3(config-if)#no shutdown
R3(config-if)#exit
R3(config)#exit
R3#s
*Jul 15 11:04:59.174: %SYS-5-CONFIG_I: Configured from console by console
R3#show ip interface brief
Interface                IP-Address      OK? Method Status      Protocol
Ethernet0/0              40.0.0.1        YES manual up          up
Ethernet0/1              30.0.0.2        YES manual up          up
Ethernet0/2              unassigned      YES TFTP  down        down
Ethernet0/3              unassigned      YES TFTP  down        down
R3#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#ip route 10.0.0.0 255.0.0.0 30.0.0.1
R3(config)#ip route 20.0.0.0 255.0.0.0 30.0.0.1
R3(config)#exit
R3#show
*Jul 15 11:07:21.552: %SYS-5-CONFIG_I: Configured from console by console
R3#show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2
       i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
       ia - IS-IS inter area, * - candidate default, U - per-user static route
       o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
       a - application route
       + - replicated route, % - next hop override, p - overrides from PfR

Gateway of last resort is not set

S    10.0.0.0/8 [1/0] via 30.0.0.1
S    20.0.0.0/8 [1/0] via 30.0.0.1
     30.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
C    30.0.0.0/8 is directly connected, Ethernet0/1
L    30.0.0.2/32 is directly connected, Ethernet0/1
     40.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
C    40.0.0.0/8 is directly connected, Ethernet0/0
L    40.0.0.1/32 is directly connected, Ethernet0/0
R3#
```

37°C

