CS1021 Tutorial 6

Reading and Writing to Memory

Q1 if a, b and c are 32bit signed integers stored at memory addresses 0x40000000, 0x40000004 and 0x40000008 respectively, write ARM assembly language instructions to compute:

```
(i)
      a = a + b
(ii)
      c = a - b
      LDR
                RO, =0x40000000
                                         ; R0 -> a
      LDR
                RO, [RO]
                                         ; R0 = a
                R1, =0x40000004
      LDR
                                         ; R1 -> b
      LDR
                R1, [R1]
                                         ; R1 = b
      SUB
                RO, RO, R1
                                         ; R0 = a - b
      LDR
                R1, =0x40000008
                                         ; R1 -> c
      STR
                RO, [R1]
                                         ; c = R0 = a - b
```

(iii) Assignment Project Exam Help

Q2 If a, b and c are 256 bit integers stored at memory addresses 0x40000000, 0x40000020 and 0x40000040 respectively, write ARM assembly language instructions to compute:

```
(i) a=a|bhttps://powcoder.com
```

(ii) c = a & b

```
; Add WeChat powcoder ; a 256-bit integer occupies 256/32 = 8 x 32 bit words
; R1 -> a
; R2 -> b
; R3 -> c
                R1, =0x40000000 ; R1 \rightarrow a
      LDR
      LDR
                R2, =0x40000020 ; R2 -> b
      LDR
                R3, =0x40000040 ; R3 \rightarrow c
      LDR
                R4, =8
                                    ; cnt = 8 (8 words)
L
      LDR
                RO, [R1]
                                    ; R0 = a
                R5, [R2]
                                    ; R5 = b
      LDR
      AND
                RO, RO, R5
                                    ; R0 = a \& b
      STR
                R0, [R3]
                                    ; c = R0 = a \& b
      ADD
                R1, R1, #4
                                    ; R1 -> next word of a
      ADD
                R2, R2, #4
                                    ; R2 -> next word of b
      ADD
                R3, R3, #4
                                    ; R3 -> next word of c
      SUBS
                R4, R4, #1
                                    ; cnt -= 1 and set flags
      BNE
                                     ; next word if cnt != 0
```

(iii) c = a + b

Q3 If a zero terminated string of ASCII characters is stored at memory address 0x40000000, write ARM assembly language instructions to count the number of characters in the string (not including the zero). For example, if the string of ASCII characters is 0x31 0x32 0x33 0x00, its length is 3.

```
; R0 = length
; R1 -> s
      LDR
                R0. = 0
                                   ; length = 0
                                   ; R1 -> s
      LDR
                R1, =0x40000000
L
      LDRB
                R2, [R1]
                                   ; load next byte of string
      CMP
                R2, #0
                                   ;0?
                                   ; finished if 0
      BEO
                L1
      ADD
                RO, RO, #1
                                   ; length += 1
      ADD
                R1, R1, #1
                                   ; R1 -> next byte in s
                                   ; next byte
      В
L1
```

Q4 If a zero terminated string of ASCII characters is stored at memory address 0x40000000, write ARM assembly language instructions to store the string in reverse order at memory address 0x40001000. For example, if the string of ASCII characters is 0x31 0x32 0x33 0x00 the reverse string stored at memory location 0x40001000 is 0x33 0x32 0x31 0x00.

If a zero terminated string of ASCII characters is stored at memory address 0x40000000, write ARM assembly language instructions to reverse the string in situ (without using any other memory locations).

https://powcoder.com

; R2 -> last byte of string (excluding terminating zero)

Q5

```
; find last by ddring We Chat powcoder
```

```
LDR
                R1, =0x40000000 ; R1 \rightarrow s
      MOV
                R2. R1
                                   : R2 -> s
      LDRB
                                    ; load next byte of string
L
                R0, [R2]
      CMP
                RO, #0
                                   ;0?
      BEQ
                L1
      ADD
                R2, R2, #1
                                   ; R1 -> next byte in s
      В
                                   ; next byte
L1
      SUB
                                   ; R2 = R2 - 1
                R2, R2, #1
; swap first and last bytes and work towards middle
L2
      CMP
                R1, R2
      BHS
                                    ; if R1 >= R2 then finished
                L3
      LDRB
               R0, [R1]
                                    ; swap bytes
      LDRB
                R3, R21
      STRB
                RO, [R2]
      STRB
                R3, [R1]
      ADD
                R1, R1, #1
                                    ; R1 = R1 + 1
      SUB
                R2, R2, #1
                                   ; R2 = R2 - 1
      В
                L2
L3
```