DASH GCP VM Access Guide

Input Guide

This section outlines the input parameters required for provisioning GCP Virtual Machines using the DASH Portal. Each parameter includes a description, available options, usage guidance, and notes on valid combinations when applicable.

Input Parameter	Description	Values Provided	Value Guidance	Valid Combinations
os_template	Pre-configured base Operating System image used for the VM.	ubuntu-2004-lts, ubuntu-2204-lts, ubuntu-2404-lts, rhel-9, rhel-8, windows-2019, windows-2022	Choose an OS required for your workload.	N/A
machine_type	GCP VM size to allocate.	n1-standard-1, n1-standard-2, n1-standard-8, n2-standard-4, e2-standard-2, e2-standard-4	Choose based on workload requirements (vCPU, memory).	N/A
region	GCP region where the VM will be deployed.	us-central1, us-west1, us-east1	Choose the region that is geographically closest to your end users or integrated services to minimize latency and improve performance.	N/A
service_name	The name of the service to install on the VM.	docker, minio, mongodb, nfs, nginx, postgres, kubernetes, llavallm, none	Choose based on the role the VM will serve (eg: Docker for container hosts, Postgres for DB)	N/A
hostname	A unique name to identify the VM.	Any alphanumeric string with dashes	Use clear naming conventions for easier resource management.	N/A

Sample Input Selection:



Output Guide

This section outlines the output values generated after GCP Virtual Machine provisioning through the DASH Portal. These outputs can be used to access, manage, and connect to your virtual machine.

Outputs	Description	Example Value
Authentication	Connect to VM directly using external_ip.	ssh dash@35.202.249.240
connection_info	Connect to the VM using gcloud-cli.	gcloud compute ssh dash-demogcpv-yavb-001 --project dash-gcp-services --zone us-central1-a
external_ip	Public IP address of the VM.	35.202.249.240
loadbalancer_endpoint	Frontend IP to access the application in the host	http://34.54.97.200

	machine.	
network_ip	Private IP address of the VM.	10.30.0.46
Password	Password to SSH into the VM.	h51wKjtf
Username	Username to SSH into the VM.	dash

Steps to SSH to GCP Virtual Machine:

Use the below commands to connect to GCP Virtual Machine.

1. **SSH to the Virtual Machine using Public IP : (Linux-based OS)**
   - Copy the value of the Authentication displayed in output and run the command in the terminal.

     Example: ssh dash@35.202.249.240

2. **RDP into the Virtual Machine (Windows-based OS)**
   - Open Remote Desktop Connection (mstsc on Windows).
   - Enter the Public IP Address (e.g., 35.202.249.240).
   - Use the username (Username) and password (Password) from the outputs.

3. **Login to Virtual Machine from Local Machine using gcloud: (applicable only for users with access to Google Cloud Platform)**
   - Install Google Cloud SDK on your local machine: Install instructions.
   - Initialize gcloud (one-time setup): gcloud init
   - Login to the VM via SSH: gcloud compute ssh <VM_NAME> --project <PROJECT_ID> --zone <ZONE>

Example: gcloud compute ssh dash-demogcpv-yavb-001 --project dash-gcp-services --zone us-central1-a