



A screenshot of a terminal window titled 'h2dpscuc@login02:~'. The terminal shows the following output:

Activate the web console with: systemctl enable --now cockpit.socket

Last login: Thu Sep 3 17:00:53 2026 from 157.45.228.76

Google Authenticator Setup Required

Generating new secret...

A large QR code is displayed in the center of the terminal. Overlaid on the QR code is the text 'ONLY FOR DEMO' in large, bold, black capital letters.

At the bottom of the terminal, the text 'Your new secret key is: T60S0F1 KC04EPY54Z3B0TEYU12FK1 0DF' is visible.

- 5) Open the Google Authenticator app on your phone and tap the “+”, then tap on “Scan a QR Code”.
- 6) Once scanned a new entry will appear on the app similar to the following,

login02:h2dpscuc@login02

- 7) Verify the setup using the 6-digit code appearing on the app, this will be auto generated every 30 seconds.
- 8) Keep the emergency scratch codes in a safe place for future emergencies.

Step 3: Logging in after Setup

For all future logins,

- 1) Enter the Captcha
- 2) Enter the 6-digit code from Google Authenticator app
- 3) Enter your password

Step 4: Regenerating the QR Code/Secret Key

If you need to reset your Google Authenticator setup (e.g., lost phone, reinstall):

- 1) Log in to the cluster and run: google-authenticator

This will:

- a. Generate a new secret key
 - b. Display a new QR code (scan this with Google Authenticator app)
 - c. Provide backup codes (emergency codes)
- 2) Follow the prompts:
 - a. Update .google_authenticator file → y
 - b. Disallow multiple uses → y
 - c. Increase window size → y
 - d. Enable rate-limiting → y

4. A file ~/.google_authenticator will be created in your home directory.

△ Important: Save the 4–5 emergency backup codes somewhere safe (e.g., offline notebook or password manager). These can be used if your phone is unavailable.

Note

- 1) Always keep your phone with Google Authenticator accessible when logging in.
- 2) Do not share your QR code, secret key, or emergency codes with anyone.
- 3) If you lose access to your authenticator app and emergency codes, contact the system administrator to reset your 2FA.