AEM Task -3 Documentation


By Priyanka

1. Create an Author Component

Steps:

Navigate to AEM CRXDE Lite

 Go to /apps/project/components/author and create a new component.




Add a cq:dialog node for the configuration dialog.

Define Dialog Fields

- Add the following fields under cq:dialog/content/items
 - Author Name: Single-line text field (granite/ui/components/foundation/form/text) → Set required.
 - Author Bio: Multi-line text field (granite/ui/components/foundation/form/textarea) → Set required.
 - DOB: Date picker (granite/ui/components/foundation/form/datepicker) → Set required.







2. Fetch Values Using HTL Properties

Steps:

Inside the component HTML file (author.html), use HTL (data-sly-use) to fetch values.

Use HTL properties like:

- \$\{\text{properties.authorName}\}
- \$\{\text{properties.authorBio}\}
- \$\{\text{properties.dob}\}

С

3. Dialog Validation

What is Dialog Validation?

- Dialog validation ensures that required fields are filled before submitting the dialog.
- To enable validation, set the property required to true in each dialog field.

4. Implement ClientLib

What is ClientLib?

• A Client Library (clientlib) in AEM is used to manage JavaScript and CSS.

Steps:

- 1. Create clientlib under /apps/project/components/author.
- 2. Add a css.txt and author.css file to style the component.
 - Make authorName an h1 tag.
 - Make authorBio a normal body text.
 - Bold the dob field.
- 3. Include clientlib in the component using:

<cq:includeClientLib categories="author-styles" />

5. ExtraClientLib & Custom ClientLib

What is ExtraClientLib?


• extraClientLibs allows adding additional client libraries at runtime.


How to Create & Use?

- 1. Define an extraClientLib in the component properties.
- 2. Load it dynamically in the cq:dialog.
- 3. Use data-sly-use to access the extra client libraries in HTL.


6. Testing and Deploying


- Save all changes and deploy the component.
- Test the Author Component in AEM.
- Add component to the AEM site inside the myTraining > us > en, select edit and add component author.





• Provide Properties to the component





And display the result.

