Structure for AmeboChat

More features will be added by the community (you) as we progress.

Models

Object

properties: id, created_at
subclasses:

Profile

properties: **display_name**, **description**, **avatar** (image) plus **Objects** properties too. subclasses:

User

properties: unique_id, password, last_seen, status. direct_messages, groups, broadcast_channels. unique_id can be anything like username, email, phone number, NIN, matric number etc.

subclasses:

Bot

properties: api_key

Room

properties: messages, members, pinned_message subclasses:

- SubRoom
- Group

properties; creator, roles
subclasses:

Broadcast

It's a type of **Group** but the **SEND_MESSAGE** permission is restricted and not available for everyone.

- Role
- Message

properties: author, text, attachments, reply_message_id, forwarded, forwarder, frowarded_fro.

subclasses:

DirectMessage

properties: recipient

■ RoomMessage

properties: room_id, room_type

SubRoomMessage

properties: main_room_id

Messaging Channels

• DIRECT MESSAGE

The one on one type of messaging.


GROUPS

A room where many people chat simultaneously.

SUBGROUPS

A smaller room created by privileged person's in the room for special purpose. e g a sub group for admins in the room (no need to create another group for admins) Like we have on AmeboChat, AmeboUl, AmeboServer groups differently,

AmeboChat will just be the mother group and the other teams group will be



sub groups just like in discord.

BROADCAST

Exactly like **GROUPS** but the **EVERYONE** Permission is revoked, so not everyone can contribute in the channel, they just react to the messages.

PERMISSIONS

MANAGE_ROOM

Manage room details and everyother thing in the room, the highest permission. Manage everyother permissions in this room.

MANAGE_ROLES

Manage the roles in the room, add or delete roles, add or remove members to or from a role. also manage the permissions of each roles.

MANAGE_MESSAGES

Manage messages in the room, delete messages or pin message.

• MANAGE_MEMBERS

Manage members in the room, add or delete members to or from the room.

• MANAGE_SUBGROUPS

Manage subgroups, add or delete subgroups, change avatar, name and description of subgroups

• MANAGE_INVITES

Have access to the room invite link, and can add members to the room, but can't delete them from the room.

• SEND MESSAGES

Able to send messages in the room

• EMBED_LINKS

Make links send into the room clickable, when a member without this permission send a message that has a link in it, the link won't be clickable from the app.

• ATTACH_FILES

Able to send files into the room (images, audio, pdf, doc etc).

ACTIONS

SIGN

• SIGN_IN

- SIGN_UP
- SIGN_OUT

SUB_GROUP

- CREATE_SUB_GROUP
- DELETE_SUB_GROUP
- SET_ROLE

Role that can be in this group. People with this role in the main group will be able to interact in this subgroup.

• SET_VISIBILITY

Whether to hide this subgroup from people without the assigned role.

GROUP

BROADCAST also has its own by replacing GROUP with BROADCAST in the following actions.

- CREATE_GROUP
- ADD_MEMBER
- REMOVE_MEMBER
- BAN_MEMBER
- ADD_ROLE
- REMOVE_ROLE
- SET_MEMBER_ROLE
- REMOVE_MEMBER_ROLE
- EDIT_GROUP_INFO
- EDIT_GROUP_AVATAR
- EDIT_GROUP_NAME
- EDIT_GROUP_DESCRIPTION
- CREATE_GROUP_INVITE_LINK
- REVOKE_GROUP_INVITE_LINK
- JOIN_GROUP
- LEAVE_GROUP
- DELETE_GROUP
- SET_PINNED_MESSAGE
- SEND_MESSAGE_TO_GROUP

MESSAGE

- DELETE_MESSAGE
- CLEAR_MESSAGES
- FORWARD_MESSAGE
- EDIT_MESSAGE
- REPLY_TO_MESSAGE
- MESSAGE_STATE

Whether message is sent, delivered, or read.

• USER

- CREATE_USER
- EDIT_USER_INFO
- EDIT_USER_NAME
- EDIT_USER_AVATAR
- EDIT_USER_DESCRIPTION
- DELETE_USER