Keyboard shortcuts

Keyboard shortcuts are combinations of keys that allow you to perform actions, such as opening the settings dialog or accessing a feature inside *Terminal* quickly. These shortcuts can be modified to suit your preferences.

To change a keyboard shortcut:

- 1. Press the menu button in the top-right corner of the window and select Preferences.
- 2. In the sidebar, select Shortcuts.
- 3. Make sure Enable shortcuts is selected.
- 4. Select the shortcut that you wish to edit by clicking on it.
- 5. Once the shortcut is selected, click on the shortcut key combination to edit it.
- 6. Press your desired shortcut key combination as you would enter it to use it. The keys that you can use include Alt , Alt Gr , Ctrl , Shift , Super , number and letter keys.
 - Mnemonic key combinations, such as Alt + F will not work.
- 7. Once you have entered your new shortcut, it will automatically be saved and you should see it in the list next to the corresponding action.
- To disable a shortcut, edit it and press the Backspace instead of the new shortcut.

File shortcuts

The default shortcuts for options in this section are:

Action	Keyboard Shortcut	
New Tab	Shift + Ctrl + T	
New Window	Shift + Ctrl + N	
Close Tab	Shift + Ctrl + W	
Close Window	Shift + Ctrl + Q	

Edit shortcuts

The default shortcuts for options in this section are:

Action	Action Keyboard Shortcut		
Сору	Shift + Ctrl + C		
Paste	Shift + Ctrl + V		

View shortcuts

The default shortcuts for options in this section are:

Action	Keyboard Shortcut
Full Screen	F11
Zoom In	Ctrl + +
Zoom Out	Ctrl + -
Normal Size	Ctrl + 0

Search shortcuts

The default shortcuts for options in this section are:

Action	Keyboard Shortcut	
Find	Shift + Ctrl + F	
Find Next	Shift + Ctrl + G	
Find Previous	Shift + Ctrl + H	
Clear Highlight	Shift + Ctrl + J	

Tab shortcuts

The default shortcuts for options in this section are:

	Action	Keyboard Shortcut
--	--------	-------------------

Switch to Previous Tab	Ctrl + Page Up
Switch to Next Tab	Ctrl + Page Down
Move Tab to the Left	Shift + Ctrl + Page Up
Move Tab to the Right	Shift + Ctrl + Page Down
Switch to Tab 1	Alt + 1
Switch to Tab 2	Alt + 2
Switch to Tab 3	Alt + 3
Switch to Tab 4	Alt + 4
Switch to Tab 5	Alt + 5
Switch to Tab 6	Alt + 6
Switch to Tab 7	Alt + 7
Switch to Tab 8	Alt + 8
Switch to Tab 9	Alt + 9
Switch to Tab 10	Alt + 0

Other

There are also some shortcuts that cannot be edited:

Action	Keyboard Shortcut	
Scroll up by one line	Shift + Ctrl + Up	
Scroll down by one line	Shift + Ctrl + Down	
Scroll up by one page	Shift + Page Up	
Scroll down by one page	Shift + Page Down	
Scroll to the top	Shift + Home	
Scroll to the bottom	Shift + End	

Bash shortcuts

These are Bash shortcuts. Bash is usually the default shell.

Bash shell specific keyboard shortcuts are:

Action	Keyboard shortcut
Erase a word	Ctrl + W
Erase a line	Ctrl + U
Move to the start of the line	Ctrl + A
Move to the end of the line	Ctrl + E
Move back one character	Ctrl + B
Move back one word	Alt + B
Move forward one character	Ctrl + F
Move forward one word	Alt + F
Delete from the cursor to the beginning of the line	Ctrl + u
Delete from the cursor to the end of the line	Ctrl + K
Delete from the cursor to the start of the word	Ctrl + W
Delete previous word	Alt + Backspace
Paste text from the clipboard	Ctrl + Y
Clear the screen leaving the current line at the top of the screen	Ctrl + L
Reverse incremental search of history	Ctrl + R
Reverse non-incremental search of history	Alt + P

More Information

Advanced Settings

Global Preferences

See Also

Copy and paste — Copy and paste text in *Terminal*.

Keyboard accessibility — Navigate around *Terminal* menus using keyboard keys.