





Jul 19, 2022

S Bjerrum Schafer-Nielsen buffer, modified by DING LAB, v1.0

Pingtao Ding¹

¹Institute of Biology Leiden, Leiden University



dx.doi.org/10.17504/protocols.io.3byl4bnzzvo5/v1

Ding Lab

Ding Lab IBL Leiden University

DISCLAIMER

DISCLAIMER - FOR INFORMATIONAL PURPOSES ONLY; USE AT YOUR OWN RISK

The protocol content here is for informational purposes only and does not constitute legal, medical, clinical, or safety advice, or otherwise; content added to protocols.io is not peer reviewed and may not have undergone a formal approval of any kind. Information presented in this protocol should not substitute for independent professional judgment, advice, diagnosis, or treatment. Any action you take or refrain from taking using or relying upon the information presented here is strictly at your own risk. You agree that neither the Company nor any of the authors, contributors, administrators, or anyone else associated with protocols.io, can be held responsible for your use of the information contained in or linked to this protocol or any of our Sites/Apps and Services.

ABSTRACT

This is a modified transfer buffer recipe for a semi-dry Western blot.

DOI

dx.doi.org/10.17504/protocols.io.3byl4bnzzvo5/v1

PROTOCOL CITATION

Pingtao Ding 2022. Bjerrum Schafer-Nielsen buffer, modified by DING LAB, v1.0. **protocols.io**

https://dx.doi.org/10.17504/protocols.io.3byl4bnzzvo5/v1



FUNDERS ACKNOWLEDGEMENT

R-ELEVATION, European Research Council (ERC) under the European Union's Horizon Europe research and innovation programme

Grant ID: 101039824

LICENSE

This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

CREATED

Jul 19, 2022

LAST MODIFIED

Jul 19, 2022

PROTOCOL INTEGER ID

67041

DISCLAIMER:

DISCLAIMER - FOR INFORMATIONAL PURPOSES ONLY; USE AT YOUR OWN RISK

The protocol content here is for informational purposes only and does not constitute legal, medical, clinical, or safety advice, or otherwise; content added to <u>protocols.io</u> is not peer reviewed and may not have undergone a formal approval of any kind. Information presented in this protocol should not substitute for independent professional judgment, advice, diagnosis, or treatment. Any action you take or refrain from taking using or relying upon the information presented here is strictly at your own risk. You agree that neither the Company nor any of the authors, contributors, administrators, or anyone else associated with <u>protocols.io</u>, can be held responsible for your use of the information contained in or linked to this protocol or any of our Sites/Apps and Services.

proportion guide

1 [M]48 millimolar (mM) Tris Base [M]39 millimolar (mM) Glycine [M]15 % volume Isopropanol

p**⊦9.2**

This recipe is modified from the original Towbin (1979) buffer, with increased Tris base but

protocols.io

2

reduced glycine.

This recipe is suitable for semi-dry transfer, and ideal for SDS-PAGE and 2-D PAGE.

References:

Garfin DE and Bers G (1989). Basic aspects of protein blotting. In Protein Blotting: Methodology, Research and Diagnostic Applications, B.A. Baldo et al., eds. (Basel, Switzerland: Karger), pp. 5–41.

Towbin H et al. (1979). Electrophoretic transfer of proteins from polyacrylamide gels to nitrocellulose sheets: procedure and some applications. Proc Natl Acad Sci USA 76, 4350–4354.

2 for **1 L 10x stock buffer**

add in a 2 L beaker

■58.2 g Tris Base

29.3 g Glycine

add up to 300 mL ddH20 , stir and mix well until all salts are fully dissolved

measure pH, and it should reach around pF9.2

top up with ddH20 to 11 L

3 before using, dilute the 10x stock buffer into 1x working buffer

for 1 L working solution

take 100 mL 10x stock buffer

add 150 mL Isopropanol

top up to 11 L with ddH20

In the original recipe, the working buffer uses 20% ethanol, but here we changed it to 15% isopropanol.

- 4 Tips (modified from Bio-Rad: https://www.bio-rad.com/webroot/web/pdf/lsr/literature/Bulletin_6211.pdf):
 - 1. Use high-quality, analytical grade reagents to enable better buffer conductivity and hence better transfer.
 - 2. If reusing the buffer, measure the pH before use and make sure it maintains at p+9.2.
 - 3. Do not further dilute the transfer buffer from 1x to the levels below the recommended concentration, because this decreases the buffering capacity of the buffer.
 - 4. Do not adjust the pH of the buffer, because it can result in increased buffer conductivity,



manifested by higher initial current output and decreased resistance.

- 5. There is no SDS in this recipe, but it can be added when it is necessary. Increasing SDS in the transfer buffer increases protein transfer from the gel but decreases the binding of the protein to the nitrocellulose membrane. In this case, nitrocellulose membrane can be substituted by PVDF membrane when SDS is used in the transfer buffer.
- 6. Addition of SDS increases the relative current, power, and heating during transfer, and may also affect the antigenicity of some proteins.
- 7. Increasing alcohol in the transfer buffer decreases protein transfer from the gel and increases the binding of the protein to the nitrocellulose membrane.