

Microsoft word

Microsoft word is a word processing program that allows for the creation of both simple and complex documents. With office 365, you are able to download the application to your hard drive and will also have access to the online version.

Microsoft word table

A table is a grid of cells arranged in rows and columns. Tables can be used to organize any type of content, whether you're working with text or numerical data. In word, you can quickly insert a blank table or convert existing text to a table. you can also customize your table using different styles or layouts. Tables are used to organize data that is too detailed or complicated to be described adequately in the text, allowing the reader to quickly see the results. They can be used to

highlight trends or patterns in the data and to make a manuscript more readable by removing numeric data from the text.

Select insert > table and then select convert text to table. To draw your own table select insert > table > draw table.

Parts of table

The main parts of table are following

- Table number
- Title
- Head note
- Stub head
- Stub entries
- Column heading
- Body of the table
- foot note
- Source

The MS tables can be used to align numbers in columns and then various operations can be performed on them.

Making table in MS word

The tables are very useful tools when creating and formatting documents. for example,

with a table you can:

⇒ Align text, Numbers and Graphics

Many people prefer to use tables for the alignment instead of tab stops because text can wrap to multiple lines in a table.

⇒ Create a form

You can use tables to store lists of telephone numbers, clients and employee rosters.

⇒ Share information

You can use tables to share information between programs. for example, you can copy and paste a table's information into a MS Excel, worksheet or access database.

Day: _____

Date: _____

⇒ Create a publication

Tables make it easier to create calendars, brochures, business cards and many other publications.

⇒ Insert a table

To create a table you must first determine how many columns (which run up and down) and rows (which run up left to right) you want to appear in your table. Cells are small, rectangular boxes where the rows and columns intersect. The number of columns and rows determines the number of cells in a table.

- click the insert tab
- click the table button
- use the grid to select how many columns and rows you'd like. The table with the specified number of rows and columns is inserted
- Enter your content into your newly created table.

you can use the arrow

keys to navigate from cell to cell as you type you can also press the Tab key to move to the next cell.

→ Select cells

you can select a single cell in a table, or you can select multiple cells, entire rows or columns, or the entire table.

● Select a single cell

click in the lower-left corner of a cell. when the cursor changes to an arrow (↖). Click and drag to select multiple cells. you can also triple-click a cell, or place your text cursor within a cell, click the select button on the table tools layout tab and choose select cell from the menu.

● Select a row

click to the left of the table row, just outside of the table itself. you can also place your text cursor within a cell - click the select button on the table tools layout tab and choose select row from the menu.

● select a column

click above a column. when the cursor changes to an arrow (↓). you can also place your text cursor within a cell. click the select button on the table tools layout tab and choose select column from the menu.

● select an entire table

Click the table selector.  button in the upper-left corner of a table. you can also place your text cursor within a cell. click the select button on the table tools layout tab and choose select table from the menu.

→ Add a row or column

You can add more columns and rows to a table after you've inserted it. This way you are not trapped using a fixed structure if you need to add more data later.

● select a cell in a row or column

adjacent to where you want the new row or column inserted.

- Click the layout tab in the table tools ribbon group.
- Click one of the Insert buttons in the rows and columns group.

you can insert a row above or below the selected cells rows or a column to the left or right of the selected cells column.

⇒ Delete a row or column

you can delete rows and columns that you don't want, in case you made a table that was bigger than you needed.

- select a cell in a row or column you want to delete.
 - Click the Delete button on the layout tab in the table tools ribbon group.
- Here,


you have the option to delete the specific cell, the column or row the selected cells is in or an entire table.

Create a table using the table grid

To insert a table using Insert table and select columns and rows in the Table Grid.

- Click in the word document where you want to insert a table.
- Click the insert tab in the Ribbon.
- Click Table in the Tables group. A drop-down menu appears with a table grid.
- Hovers over the grid until the number of columns and rows you want is selected.
- Click in the high lighted area of the grid to insert a table.

To insert a table select cells in the table grid as follows



Create a table using the Insert table dialog box

To insert a table using the insert table dialog box

- Click in the word document where you want to insert a table
- Click the insert tab in the Ribbon
- Click tables in the Tables group. A drop-down menu appears.
- ⇒ ● Select insert table. A dialog box appears
- Enter the number of columns and rows you want to create
- Select the desired options below Autofit behaviour (typically fixed column width: Auto)
- Click OK.

The insert table dialog box appears with options to select the number of columns and rows:

Insert Table	
Table size	
Number of columns	5
Number of rows	2
Autofit behaviour	
☒ Fixed column width	Auto
☐ Autofit to contents	
☐ Autofit to window	
Remember dimension new table	
OK	Cancel

Create a table using Quick tables

To insert a table using Quick tables

- Click in the word document where you want to insert a table
- Click the Insert tab in the Ribbon
- Click table in the Tables group. A drop-down menu appears
- Select Quick tables. A gallery appears
- Click the table you want to insert

Create a table by converting text to a table

- Select the text that you want to convert
- Click the Insert tab in the Ribbon
- Click table in the Tables group. A drop down menu appears
- Select convert text to table. A dialog box appears
- Enter the number of columns if dialog box appears

- Enter the number of columns if necessary and ensure a delimiter is selected in the separate text area.
- Under Auto-fit behaviours, choose how you want your table to appear. Word chooses a width for the table columns by default. If you want a different column width, choose Auto-fit contents or Auto-fit to window.
- Click OK.


In the Convert text to table dialog box, enter the number of columns as well as delimiter.

Show table gridlines

Gridlines show the cell boundaries of a table on screen if table borders are not applied. Gridlines appear only on the screen and are not printed. The Gridlines are not visible when you view a document in a web browser or in print preview.

To show table gridlines in a word document

- Click in a table
 - Click the table layout or table tools layout tab in the Ribbon
- In the Table group, check view gridlines



Change Column width

Select the column or columns you want to change

- Click the Table layout or table tools layout tab in the Ribbon
- Click properties in the Table group you can also right-click and choose properties from the drop-down menu. A dialog box appears
- Click the column tab
- Check preferred width
- Type the new measurement for the column width. for example, types 1.0"

- or click the up and down arrows
- Click ok

Change row height

- Select the row or rows you want to change
- Click the table layout or table tools layout in the Ribbon
- Click properties in the table group. you can also right click and choose properties from the drop-menu appears. A dialog box appears
- Click the row tab
- Check specify height
- Type the new measurement for the row height for example type 1.0" or click the up and down arrows
- specify row height as at least or exactly
- Click ok.

Apply a table style

- Click in the table

- Click the table design or table tools design tab in the Ribbon
- Click a table style or click the more arrow to display the table styles gallery and click a style

Distribute rows and columns evenly

To distribute rows and columns evenly

- Select the entire table by clicking the four-arrows that appear on the top of the table.
- Click the table layout or table tools layout tab in the Ribbon
- Click the distribute rows and/or distribute columns in the cell size group.