Proj2

Release 1.0

PuckVG

CONTENTS:

1	Project2	1
	1.1 nn package	
	Indices and tables	7
Ру	ython Module Index	9
In	ndex	11

CHAPTER

ONE

PROJECT2

1.1 nn package

1.1.1 Submodules

1.1.2 nn.activation module

```
class nn.activation.Activation
     Bases: nn.module.Module
     backward(dy)
          Compute gradients of input.
              Parameters dy (torch.tensor) – Backpropagated gradient from the next layer.
              Returns Gradient
              Return type grad (torch.tensor)
     forward(x)
          Compute the activation.
              Parameters \mathbf{x} (torch.tensor) – Input tensor.
class nn.activation.ReLU
     Bases: nn.activation.Activation
     ReLU activation function
     forward(x)
          Compute the activation.
              Parameters \mathbf{x} (torch.tensor) – Input tensor.
              Returns Output tensor.
              Return type out (torch.tensor)
class nn.activation.Tanh
     Bases: nn.activation.Activation
     Tanh activation function
     forward(x)
          Compute the activation.
              Parameters \mathbf{x} (torch.tensor) – Input tensor.
              Returns Output tensor.
```

Return type out (torch.tensor)

1.1.3 nn.functional module

```
The functional.py contains the concrete implementations of specific functionals.
```

```
nn.functional.\mathbf{d}_mse(x, y)
```

Compute the gradient of the mean squared error.

Parameters

- **x** (torch.tensor) Input tensor.
- y (torch.tensor) Target tensor.

Returns Gradient of mean squared error.

Return type d_mse (float)

```
nn.functional.\mathbf{d}_relu(x)
```

Compute gradient of ReLU(x)

Parameters x (torch.tensor) - Input tensor

Returns Output tensor

Return type out (torch.tensor)

nn.functional.d_tanh(x)

Compute gradient of tanh(x)

Parameters x (torch.tensor) – Input tensor

Returns Output tensor

Return type out (torch.tensor)

nn.functional.mse(x, y)

Compute the mean squared error.

Parameters

- **x** (torch.tensor) Input tensor.
- y (torch.tensor) Target tensor.

Returns Mean squared error.

Return type ms_error (torch.tensor)

nn.functional.relu(x)

Compute ReLU(x)

Parameters x (torch.tensor) - Input tensor

Returns Output tensor

Return type out (torch.tensor)

nn.functional.tanh(x)

Compute tanh(x).

Parameters x (torch.tensor) - Input tensor

Returns Output tensor

Return type out (torch.tensor)

1.1.4 nn.linear module

```
class nn.linear.Layer
     Bases: nn.module.Module
     param()
          Return the params of the Layer.
     update_param(*args, **kwargs)
          Update the params of the Layer based on the cached gradients
class nn.linear.Linear(dim_in, dim_out)
     Bases: nn.linear.Laver
     backward(dv)
          Compute gradients of input and parameters.
               Parameters dy (torch.tensor) – Backpropagated gradient from the next layer.
               Returns Gradient.
               Return type output (torch.tensor)
     forward(x)
          Calculate output.
               Parameters x (torch.tensor) - Input tensor of size (batch_size, input_dim)
               Returns Output tensor of size (batch_size, output_dim)
               Return type output (torch.tensor)
     param()
          Get parameters of the linear layer from the cache.
               Returns weight and bias of linear layer.
               Return type w, b (torch.tensor)
nn.linear.empty(*size,
                             *, out=None,
                                             dtype=None, layout=torch.strided, device=None,
                      quires grad=False, pin\ memory=False) \rightarrow Tensor
     Returns a tensor filled with uninitialized data. The shape of the tensor is defined by the variable argument size.
          Parameters size (int...) – a sequence of integers defining the shape of the output tensor. Can
               be a variable number of arguments or a collection like a list or tuple.
          Keyword Arguments
```

- out (Tensor, optional) the output tensor.
- dtype (torch.dtype, optional) the desired data type of returned tensor. Default: if None, uses a global default (see torch.set_default_tensor_type()).
- layout (torch.layout, optional) the desired layout of returned Tensor. Default: torch.strided.
- device (torch.device, optional) the desired device of returned tensor. Default: if None, uses the current device for the default tensor type (see torch. set_default_tensor_type()). device will be the CPU for CPU tensor types and the current CUDA device for CUDA tensor types.
- requires_grad (bool, optional) If autograd should record operations on the returned tensor. Default: False.
- pin_memory (bool, optional) If set, returned tensor would be allocated in the pinned memory. Works only for CPU tensors. Default: False.

1.1. nn package 3

• memory_format (torch.memory_format, optional) - the desired memory format of returned Tensor. Default: torch.contiquous format.

Example:

```
>>> torch.empty(2, 3)
tensor(1.00000e-08 *
    [[ 6.3984,  0.0000,  0.0000],
    [ 0.0000,  0.0000,  0.0000]])
```

1.1.5 nn.loss module

class nn.loss.Loss

Bases: nn.module.Module

The Loss Module is used to implement a node in the network that computes the loss. For the computation of any function the respective functional from functional.py should be used.

backward()

Backward pass. The backward method can be implemented in the generic Loss class as it should be the same for all Loss Modules.

Returns Backpropagated gradient from the next layer.

Return type dy (torch.tensor)

forward (x, y)

Compute the loss. :param x: Input tensor. :type x: torch.tensor :param y: Target tensor. :type y: torch.tensor

class nn.loss.MSELoss

Bases: nn.loss.Loss

forward(x, y)

Compute the mean squared error.

Parameters

- **x** (torch.tensor) Input tensor.
- y (torch.tensor) Target tensor.

Returns Mean squared error.

Return type output (torch.tensor)

1.1.6 nn.module module

```
class nn.module.Module
    Bases: object
    backward(*args, **kwargs)
    forward(*args, **kwargs)
```

1.1.7 nn.sequential module

```
class nn.sequential.Sequential(modules, loss_fn)
     Bases: nn.module.Module
     backward()
          Perform backward pass.
     forward(x)
          Perform forward pass.
              Parameters x (torch.tensor) - Input tensor
              Returns Output tensor
              Return type out (torch.tensor)
     loss(x, y)
          Compute loss between two tensors.
              Parameters
                  • x (torch.tensor) - Input tensor
                  • y (torch.tensor) - Target tensor
     print()
          Print model architecture.
     test\_step(x, y)
     training_step(x, y)
          Training step.
              Parameters
                  • x (torch.tensor) - Input tensor
                  • y (torch.tensor) - Target tensor
              Returns computed loss
              Return type loss (torch.tensor)
     update_params (optim, lr)
          Update the parameters of the network iteratively according to the cached gradients at each module.
              Parameters
                  • optim (string) - The optimizer to use. options are 'adam' or 'sgd'
                  • lr (float) – Learning rate
     validation_step(x, y)
          Validation step.
              Parameters
                  • x (torch.tensor) - Input tensor
                  • y (torch.tensor) - Target tensor
              Returns computed loss
              Return type loss (torch.tensor)
```

1.1. nn package 5

1.1.8 Module contents

1.2 trainer module

class trainer.Trainer(nb_epochs)

Bases: object

fit (*model*, *x_train*, *y_train*, *x_val*, *y_val*, *batch_size=32*, *lr=0.01*, *optim='sgd'*, *verbose=True*, *print_every=32*)

Train the model on the specified data and print the training and validation loss and accuracy. :param

Train the model on the specified data and print the training and validation loss and accuracy. :param model: Module. Model to train :param dl_train: DataLoader. DataLoader containing the training data :param dl_val: DataLoader. DataLoader containting the validation data :param verbose: bool. Whether or not to output training information

test (model, x_test, y_test, batch_size=32, test_verbose=True)

Test the model on the specified data :param model: Module. Model to train :param dl_test: DataLoader. DataLoader containting the test data :param test_verbose: bool. Whether the test result should be printed

6 Chapter 1. Project2

CHAPTER

TWO

INDICES AND TABLES

- genindex
- modindex
- search

PYTHON MODULE INDEX

nnn,6 nn.activation,1 nn.functional,2 nn.linear,3 nn.loss,4 nn.module,4 nn.sequential,5 t trainer,6

10 Python Module Index

INDEX

A	nn.loss,4
Activation (class in nn.activation), 1	nn.module,4
	nn.sequential,5
В	trainer,6
backward() (nn.activation.Activation method), 1	Module (class in nn.module), 4
backward() (nn.linear.Linear method), 3	mse() (in module nn.functional), 2
backward() (nn.loss.Loss method), 4	MSELoss (class in nn.loss), 4
backward() (nn.module.Module method), 4	N
backward() (nn.sequential.Sequential method), 5	
D	nn madula 6
D	module, 6 nn.activation
d_mse() (in module nn.functional), 2	module, 1
d_relu() (in module nn.functional), 2	nn.functional
d_tanh() (in module nn.functional), 2	module, 2
E	nn.linear
	module, 3
empty() (in module nn.linear), 3	nn.loss
F	module, 4
•	nn.module
fit () (trainer.Trainer method), 6	module,4
forward() (nn.activation.Activation method), 1	nn.sequential
forward() (nn.activation.ReLU method), 1 forward() (nn.activation.Tanh method), 1	module, 5
forward() (nn.linear.Linear method), 3	Р
forward() (nn.loss.Loss method), 4	•
forward() (nn.loss.MSELoss method), 4	param() (nn.linear.Layer method), 3
forward() (nn.module.Module method), 4	<pre>param() (nn.linear.Linear method), 3 print() (nn.sequential.Sequential method), 5</pre>
forward() (nn.sequential.Sequential method), 5	print () (m. sequentiai sequentiai methoa), 3
_	R
L	ReLU (class in nn.activation), 1
Layer (class in nn.linear), 3	relu() (in module nn.functional), 2
Linear (class in nn.linear), 3	
Loss (class in nn.loss), 4	S
loss() (nn.sequential.Sequential method), 5	Sequential (class in nn.sequential), 5
M	Т
module	·
nn,6	Tanh (class in nn.activation), 1
nn.activation,1	tanh() (in module nn.functional), 2
nn.functional,2	test() (trainer.Trainer method), 6
nn.linear,3	<pre>test_step() (nn.sequential.Sequential method), 5 trainer</pre>

12 Index