

1. Connect a USB webcam to your computer, install any required drivers, and verify that the webcam works by opening the default camera app and capturing a photo.

Steps:

1. Connect the USB webcam to an available USB port.
 2. Wait for Windows to automatically detect the device.
 3. If drivers are required:
 - Open **Settings** → **Windows Update** → **Check for updates**.
 - Or install drivers from the webcam manufacturer's website.
 4. Verify installation:
 - Press **Windows + X** → **Device Manager**.
 - Expand **Cameras**.
 - Confirm the webcam name appears without a warning icon.
 5. Open the **Camera** application.
 6. Allow camera permissions if prompted.
 7. Check if live video appears.
 8. Click the **Capture** button to take a photo.
 9. Verify the photo is saved.
-
2. Set up a local printer (USB or network), install the correct driver, and print a test page to confirm successful installation.

Steps:

1. Connect the printer via USB or connect it to the same Wi-Fi network.
2. Turn on the printer.
3. Open:

Settings → **Bluetooth & devices** → **Printers & scanners**

4. Click **Add device**.
5. Select the printer.
6. Install the recommended driver if prompted.
7. Open the printer settings.
8. Click **Print a Test Page**.

3. Simulate a connectivity issue by unplugging the printer's USB cable, then use Windows Device Manager to identify and resolve the 'printer not detected' problem.

Hint: Check for error icons and use the 'Scan for hardware changes' option after reconnecting.

Simulation:

1. Unplug the printer USB cable.
2. Open **Device Manager**.
3. Expand:
 - Printers
 - Universal Serial Bus Controllers
4. Observe:
 - Missing printer
 - Yellow warning icon (if present)
5. Reconnect the USB cable.
6. In Device Manager click:

Action → Scan for hardware changes

7. Wait for Windows to detect the printer.
8. If still not detected:
 - Try another USB port.
 - Restart the printer.
 - Update or reinstall printer drivers.

4. A user reports that their webcam video is not displaying in Zoom, but it works in the default camera app. Troubleshoot and resolve the issue so the webcam works in both applications.

Hint: Check if another app is using the webcam or if Zoom permissions are enabled.

Troubleshooting Steps:

Step 1: Close Other Applications

Close applications using the webcam:

- Camera app

- Microsoft Teams
 - Google Meet
 - Skype
-

Step 2: Check Zoom Camera Selection

1. Open Zoom.
 2. Click **Settings** → **Video**.
 3. Select the correct webcam from the Camera dropdown menu.
-

Step 3: Check Camera Permissions

Open:

Settings → **Privacy & Security** → **Camera**

Enable:

Camera access

Let apps access your camera

Allow desktop apps to access your camera

Ensure Zoom is allowed.

Step 4: Restart Zoom

1. Close Zoom completely.
 2. Open **Task Manager**.
 3. End all Zoom processes.
 4. Reopen Zoom.
-

Step 5: Update Zoom

Install the latest version of Zoom.

Step 6: Update Webcam Driver

1. Open **Device Manager**.
2. Expand **Cameras**.
3. Right-click webcam.
4. Select **Update driver**.