

Instructions for installing Integrity Hash (FIM) for Windows 11

1. Installation (Windows)

1. Open the folder windows_11_installer.
2. Double-click install to begin the installation.

2. Requirements and Downloads

- If Java is not installed, or if your Java version is older than 21, press Y when prompted to install JDK 25.
- The installer will download PostgreSQL (and JDK 25).

An active internet connection is required only during installation.

Once installation is complete, the application runs fully offline.

3. PostgreSQL Password

- During installation, you will be asked to set a PostgreSQL password.
- This password will be stored in your environment variables and should not be one you use elsewhere.
- You do not need to remember this password.

Application Login

- After installation, the application will prompt you to create your Integrity Hash user account.
- This password is required to access your local server.
- It cannot be changed later. To change it, the application must be reinstalled.
- This login password is securely hashed and cannot be viewed, even with database access.

4. PostgreSQL Configuration Details

- PostgreSQL will run on a non-default port.
- It installs directly on the C: drive to avoid conflicts with any existing PostgreSQL installations.
- No services are installed; PostgreSQL will only run when the application is launched, not at system startup.

5. SSL Configuration

- SSL is automatically configured for communication between:
 - o the database and the local backend
 - o the frontend and the local backend
- Environment variables created during installation contain the necessary certificate passwords.

- The installation script provides default SSL certificates to avoid local wiretapping. Feel free to generate your own certificates now that the source code is free. Ask PWSS for help if you need support on this matter!

Do not modify or remove these variables.

6. Keys

- Open-Source License key:

Syb8qUVHcUVGYLdT15LH99nfLeO4kKZmQzV9PoelFx7TKsepgxZMGqxXSzi6mXCLjb40DID9QeapORyE
Q8TspnzlpFMS572JfkV4HkAGqBk6PDvKUMIN5+ZUgZB8dW954js9Ek4TGIRK/3rwbs1EuBJd2agyStT2Tox
5+3/LoNtrFyjNjC9QWHx9QPH4LDEP

- Endpoint code (required for baseline resets): 4350345983458934

