

#### **Command Line Interface**

Installation, help and logging in



#### Overview

- After completing this lesson, you should be able to:
  - Install the cf Command Line Interface (CLI)
  - Get help on any cf CLI command
  - Log into the Pivotal Web Services (PWS) installation

### **Topics**

- Getting Started with the Command Line Interface
- Login to Pivotal Web Services (PWS)

#### Cloud Foundry –Command Line Interface (cf CLI)

- A simple, text-based Cloud Foundry client
- Used by operators and developers to access and work with any Cloud Foundry installation
- Anything you do with the cf CLI can be scripted/automated

```
Paulchapman — bash — 87×10

Last login: Thu Mar 20 22:01:51 on ttys005
localhost:~ paulchapman$ /usr/local/bin/cf --version
/usr/local/bin/cf version 6.0.2-0bba99f
localhost:~ paulchapman$

□
```


# Installing the cf CLI

- To install the cf CLI:
  - Visit https://console.run.pivotal.io/tools
    - or https://github.com/cloudfoundry/cli
  - Download and run installer for your platform



#### Test the cf CLI Client

- The CLI is accessed with cf
  - Open a Terminal/Command/Shell window
  - At the prompt type: cf --version
  - Or use the alias: cf -v



### Getting Help- In General

- Get help at any time via cf help
- See an organized list of commands

```
PivotalCloudFoundry_ICM — bash — 151×37
greylag:PivotalCloudFoundry_ICM sbyr s$ cf help
  cf - A command line tool to interact with Cloud Foundry
  [environment variables] cf [global options] command [arguments...] [command options]
VERSION:
  6.11.1-4ef66f6-2015-04-20T21:15:38+00:00
BUILD TIME:
  2015-06-02 12:01:53.998245767 -0700 PDT
GETTING STARTED:
  login, l
                                                 Log user in
  logout, lo
                                                 Log user out
  passwd. pw
                                                 Change user password
  target, t
                                                Set or view the targeted org or space
  api
                                                Set or view target api url
  auth
                                                Authenticate user non-interactively
APPS:
                                                List all apps in the target space
  apps, a
  app
                                                Display health and status for app
  push, p
                                                Push a new app or sync changes to an existing app
  scale
                                                Change or view the instance count, disk space limit, and memory limit for an app
  delete, d
                                                 Delete an app
  rename
                                                 Rename an app
  start. st
                                                Start an app
  stop, sp
                                                Stop an app
  restart, rs
                                                 Restart an app
  restage, rq
                                                 Restage an app
  restart-app-instance
                                                 Terminate the running application Instance at the given index and instantiate a new instance of the ap
plication with the same index
```

### Getting Help- Specific Commands

• cf help <command>

```
PivotalCloudFoundry_ICM — bash — 64×10

greylag:PivotalCloudFoundry_ICM sby Mes$ cf help logout

NAME:
    logout — Log user out

ALIAS:
    lo

USAGE:
    cf logout
greylag:PivotalCloudFoundry_ICM sbyrnes$
```

## **Topics**

- Getting Started with the Command Line Interface
- Login to Pivotal Web Services (PWS)

### Pivotal Web Services (PWS)

- The cf CLI needs to point to a Cloud Foundry installation
- Pivotal provides a hosted installation at https://run.pivotal.io
- We will use this installation for part of this course
  - Visit https://run.pivotal.io
  - Sign up for a trial account



#### Login to Cloud Foundry

- The cf CLI needs to know:
  - What Cloud Foundry installation you are using
  - What your account details are
- Use cf login

```
cf login -a api.run.pivotal.io -u <username>
API endpoint: api.run.pivotal.io
Authenticating...
OK


Targeted org Cloud Foundry Course

Targeted space development

API endpoint: https://api.run.pivotal.io (API version: 2.0.0)
User: qzqz2020@yahoo.com.au
Org: Cloud Foundry Course
Space: development
```

## Finding the API Endpoint URL

- URL of your Cloud Foundry instance
  - On Apps Manager homepage on first login
  - Or click Tools
- Shows how to run cf login, including the API endpoint



#### **Current Targets**

- When you first login, you see output shown below
  - Notice it shows current organization and space
  - At any time, run cf target to get the same information
- By default your organization only has one space (development)
- Note: On PWS you are set up as your own organization and can add more organizations

```
API endpoint: https://api.run.pivotal.io (API version: 2.6.0)
```

User: pchapman@pivotal.io

Org: pivotaledu Space: development

#### Using a Proxy

- Your company may require a proxy for internet access
  - Look in the Network or Internet settings for your browser
- To configure this for cf

```
- set HTTP_PROXY=...proxyurl... (Windows)
```

- export HTTP\_PROXY=..proxyurl (Unix/MacOS)

```
localhost:dev$ set HTTP_PROXY=proxy.mycompany.com:8080


localhost:dev$ echo %HTTP_PROXY%
proxy.mycompany.com:8080
localhost:dev$

Windows
```

```
dev$ export HTTP_PROXY=proxy.mycompany.com:8080 dev$ echo $HTTP_PROXY proxy.mycompany.com:8080 dev$ Unix/MacOS
```

#### Cloud Controller

- When you set a target, you are connecting to a component of Cloud Foundry called the Cloud Controller
- The Cloud Controller has a REST API
- The commands of the cf CLI make Cloud Controller API calls behind the scenes



(the Cloud Foundry entry points of a load balancer and router are not shown in diagram)

#### The .cf Directory

- cf creates a .cf directory in your home directory of your computer
  - Stores context, logs, crash reports ...
  - Remembers your CF API endpoint
    - Don't need to specify -a option at next login

```
localhost:dev$ ls -l ~/.cf
total 48
-rw----- 1 paulchapman
                          staff
                                 2491 15 Aug 14:06 config.json
-rw-r--r-- 1 paulchapman
                                              2013 crash
                          staff
                                         Nov
drwxr-xr-x 3 paulchapman
                          staff
                                  102 12 Sep
                                              2013 logs
-rw-r--r-- 1 paulchapman
                          staff
                                   26 12 Sep 2013 target
                                              2013 tokens.yml
-rw-r--r-- 1 paulchapman
                                 2084 29 Nov
                          staff
```

## **Topics**

- Getting Started with the Command Line Interface
- Login to Pivotal Web Services (PWS)

#### Lab

Install the cf CLI and log in to PWS