

NAMA : ANANDHAKA GHIBRAN MAS

NIM : 103072400135

TCPclient.py

```
1  from socket import *
2
3  serverName = '127.0.0.1'
4  serverPort = 12000
5
6  clientSocket = socket(AF_INET, SOCK_STREAM)
7  clientSocket.connect((serverName, serverPort))
8
9  sentence = input('Input lowercase sentence: ')
10 clientSocket.send(sentence.encode())
11 modifiedSentence = clientSocket.recv(1024)
12 print('From Server: ', modifiedSentence.decode())
13
14 clientSocket.close()
```

TCPserver.py

```
1  from socket import *
2
3  serverPort = 12000
4  serverSocket = socket(AF_INET, SOCK_STREAM)
5
6  serverSocket.bind(('', serverPort))
7  serverSocket.listen(1)
8  print('The server is ready to receive')
9
10 while True:
11     connectionSocket, addr = serverSocket.accept()
12     sentence = connectionSocket.recv(1024).decode()
13     modifiedSentence = sentence.upper()
14     connectionSocket.send(modifiedSentence.encode())
15     connectionSocket.close()
```

UDPclient.py

```

1  from socket import *
2
3  serverName = '127.0.0.1'
4  serverPort = 12000
5
6  clientSocket = socket(AF_INET, SOCK_DGRAM)
7  message = input('Input lowercase sentence: ')
8
9  clientSocket.sendto(message.encode(), (serverName, serverPort))
10 modifiedMessage, serverAddress = clientSocket.recvfrom(2048)
11 print('From Server: ', modifiedMessage.decode())
12
13 clientSocket.close()

```

UDPServer.py

```

1  from socket import *
2
3  serverPort = 12000
4  serverSocket = socket(AF_INET, SOCK_DGRAM)
5  serverSocket.bind(('', serverPort))
6  print('The server is ready to receive')
7
8  while True:
9      message, clientAddress = serverSocket.recvfrom(2048)
10     modifiedMessage = message.decode().upper()
11     serverSocket.sendto(modifiedMessage.encode(), clientAddress)
12

```

OUTPUT

1. UDP CLIENT & UDP SERVER

<pre>PS C:\Users\Ryoo\OneDrive - Telkom University\Documents\Praktikum-Jarkom\Praktikum-Jarkom> cd week7 PS C:\Users\Ryoo\OneDrive - Telkom University\Documents\Praktikum-Jarkom\Praktikum-Jarkom\week7> py UDPClient.py Input lowercase sentence: Aryo From Server: ARYO PS C:\Users\Ryoo\OneDrive - Telkom University\Documents\Praktikum-Jarkom\Praktikum-Jarkom\week7></pre>	<pre>PS C:\Users\Ryoo\OneDrive - Telkom University\Documents\Praktikum-Jarkom\Praktikum-Jarkom\week7> py UDPServer.py The server is ready to receive █</pre>
--	---

2. TCP CLIENT & TCP SERVER

<pre>▼ TERMINAL PS C:\Users\Ryoo\OneDrive - Telkom University\Documents\Praktikum-Jarkom\Praktikum-Jarkom\week7> py TCPClient.py Input lowercase sentence: Ryoo From Server: RYOO PS C:\Users\Ryoo\OneDrive - Telkom University\Documents\Praktikum-Jarkom\Praktikum-Jarkom\week7></pre>	<pre>PS C:\Users\Ryoo\OneDrive - Telkom University\Documents\Praktikum-Jarkom\Praktikum-Jarkom\week7> py TCPServer.py The server is ready to receive █</pre>
--	---