Server Manager • Dashboard

Manage Tools View Help

Active Directory Users and Computers

File Action View Help

Active Directory Users and Com
- Saved Queries
- domain1.local
  - Builtin
  - Computers
  - Domain Controllers
  - ForeignSecurityPrincipal:
  - Managed Service Accour
  - Users
  - IT1
  - RD1
  - U101

Name	Type	Description
U1	User	

WELCOME TO SERVER MANAGER

BPA results   BPA results

8:23 PM
9/30/2023

Server Manager • Dashboard

Manage Tools View Help

Dashboard
- Local Server
- All Servers
- AD DS
- DNS
- File and Storage Services
- IIS
- Remote Access

WELCOME TO SERVER MANAGER

1 Configure this local server

QUICK START

2 Add roles and features

3 Add other servers to manage

4 Create a server group

WHAT'S NEW

5 Connect this server to cloud services

LEARN MORE   Hide

ROLES AND SERVER GROUPS
Roles: 5 | Server groups: 1 | Servers total: 1

AD DS	1	DNS	1
Manageability		Manageability	
Events		Events	
Services		Services	
Performance		Performance	
BPA results		BPA results	

8:24 PM
9/30/2023

Server Manager • Dashboard

Manage Tools View Help

Dashboard
- Local Server
- All Servers

WELCOME TO SERVER MANAGER

Administrator: Command Prompt

```
Microsoft Windows [Version 10.0.17763.1999]
(c) 2018 Microsoft Corporation. All rights reserved.

C:\Users\Administrator>dsmod user cn=U501,dc=domain1,dc=local -disabled yes
dsmod succeeded:cn=U501,dc=domain1,dc=local

C:\Users\Administrator>dsrm cn=U501,dc=domain1,dc=local
Are you sure you wish to delete cn=U501,dc=domain1,dc=local (Y/N)? y
dsrm succeeded:cn=U501,dc=domain1,dc=local

C:\Users\Administrator>
```

WinSer2019_1 (DC-domain1.local with Routing Enable-RIPv2) [Running] - Oracle VM VirtualBox

File Machine View Input Devices Help

Server Manager

Server Manager • Dashboard

Manage Tools View Help

Dashboard

WELCOME TO SERVER MANAGER

Active Directory Users and Computers

File Action View Help

Active Directory Users and C...
  Saved Queries
  domain1.local

Directors Properties

General Members Member Of Managed By

Members:

Name	Active Directory Domain Services Folder
U3	domain1.local
U4	domain1.local

Add... Remove

OK Cancel Apply

Hide

BPA results   BPA results

8:26 PM
9/30/2023

Right Ctrl

WinSer2019_1 (DC-domain1.local with Routing Enable-RIPv2) [Running] - Oracle VM VirtualBox

File Machine View Input Devices Help

Server Manager

Server Manager • Dashboard

Manage Tools View Help

Dashboard

WELCOME TO SERVER MANAGER

Active Directory Users and Computers

File Action View Help

Active Directory Users and Com...
  Saved Queries
  domain1.local

Name	Type	Description
201	User	
202	User	
203	User	
204	User	
205	User	
206	User	
207	User	
208	User	
209	User	
210	User	
Builtin	builtinDomain	
Computers	Container	Default container for up...
DEVs	Security Group...	
Directors	Security Group...	
Domain Con...	Organizational...	Default container for do...
ForeignSecu...	Container	Default container for sec...
Infrastructure	infrastructureU...	
IT1	Organizational...	
Keys	Container	Default container for ke...
LostAndFou...	lostAndFound	Default container for or...
Managed Se...	Container	Default container for ma...

Hide

BPA results   BPA results

8:35 PM
9/30/2023

Right Ctrl

File Machine View Input Devices Help

Recycle Bin

Network and Sharing Center

← → ✕ ↑ 🖳 « Network and Internet › Network and Sharing Center   Search Control Panel

Control Panel Home

Change adapter setting
Change advanced sharing
settings

View your basic network information and set up connections

NET1 Status

NET1 Properties

Networking

ccess type: No Internet access
onnections: 🖳 NET1

Internet Protocol Version 4 (TCP/IPv4) Properties

General

You can get IP settings assigned automatically if your network supports
this capability. Otherwise, you need to ask your network administrator
for the appropriate IP settings.

○ Obtain an IP address automatically
● Use the following IP address:
IP address: 192 . 168 . 1 . 2
Subnet mask: 255 . 255 . 255 . 0
Default gateway: 192 . 168 . 1 . 1

○ Obtain DNS server address automatically
● Use the following DNS server addresses:
Preferred DNS server: 192 . 168 . 1 . 1
Alternate DNS server: 10 . 10 . 10 . 1

☐ Validate settings upon exit   Advanced...

OK   Cancel

See also
Internet Options
Windows Defender Firewall

OK   Cancel

8:48 PM
9/30/2023

Right Ctrl

File Machine View Input Devices Help

This PC

Network

Recycle Bin

Control Panel

Network and Sharing Center

← → ✕ ↑ 🖳 « Network and Internet › Network and Sharing Center   Search Control Panel

Control Panel Home

Change adapter settings
Change advanced sharing
settings

View your basic network information and set up connections

NET1 Status

NET1 Properties

Networking

No network access
: 🖳 NET1

Internet Protocol Version 4 (TCP/IPv4) Properties

General

You can get IP settings assigned automatically if your network supports
this capability. Otherwise, you need to ask your network administrator
for the appropriate IP settings.

○ Obtain an IP address automatically
● Use the following IP address:
IP address: 172 . 16 . 1 . 4
Subnet mask: 255 . 255 . 255 . 0
Default gateway: 172 . 16 . 1 . 3

○ Obtain DNS server address automatically
● Use the following DNS server addresses:
Preferred DNS server: 172 . 16 . 1 . 3
Alternate DNS server: 10 . 10 . 10 . 1

☐ Validate settings upon exit   Advanced...

OK   Cancel

See also
Internet Options
Windows Defender Firewall

8:48 PM
9/30/2023

Right Ctrl

File Machine View Input Devices Help

Recycle Bin

This PC

Network

Control Panel

Network and Sharing Center

← → ✕ ↑ 🖳 « Network and Internet › Network and Sharing Center   Search Control Panel

Control Panel Home

Change adapter settings
Change advanced sharing
settings

View your basic network information and set up connections

NET1 Status

NET1 Properties

Networking Sharing

No network access
: 🖳 NET1
  🖳 NET2

Internet Protocol Version 4 (TCP/IPv4) Properties

General

You can get IP settings assigned automatically if your network supports
this capability. Otherwise, you need to ask your network administrator
for the appropriate IP settings.

○ Obtain an IP address automatically

● Use the following IP address:

IP address: 172 . 16 . 1 . 3
Subnet mask: 255 . 255 . 255 . 0
Default gateway: .   .   .

○ Obtain DNS server address automatically

● Use the following DNS server addresses:

Preferred DNS server: 10 . 10 . 10 . 1
Alternate DNS server: 192 . 168 . 1 . 1

☐ Validate settings upon exit   Advanced...

OK   Cancel