Simple Menu

Submitted By:
Hong Que VO
102240620
2021/03/18 11:18

Tutor:
Tuan Dung LAI

March 18, 2021

```ruby
 1  require './input_functions'
 2
 3  def maintain_albums()
 4    # whether they want to:
 5    # 1 To Update Album Title
 6    # 2 To Update Album Genre
 7    # 3 To Enter Album
 8    begin
 9      puts("Maintain Albums Menu:")
10      puts("1 To Update Album Title")
11      puts("2 To Update Album Genre")#
12      puts("3 To Enter Album")#
13      puts("4 Exit")
14      choice = read_integer_in_range("Please enter your choice:", 1, 4)
15      case choice
16      when 1
17          puts"You selected Update Album Title. Press enter to continue"
18          gets()
19      when 2
20          puts"You selected Update Album Genre. Press enter to continue"
21          gets()
22      when 3
23          puts"You selected Enter Album. Press enter to continue"
24          gets()
25      when 4
26          finished = true
27      else
28          puts('Please select again')
29      end
30      end until finished
31    end
32    # 4 Return to the main menu
33    # Implement stubs like this one for options 1 and 2
34
35  def play_existing_album()
36    puts "You selected Play Existing Album. Press enter to continue"
37    gets
38  end
39
40  # complete the case statement below and
41  # add a stub like the one above for option 2
42  # of this main menu
43  def main()
44    finished = false
45    begin
46      puts 'Main Menu:'
47      puts '1 To Enter or Update Album'
48      puts '2 To Play existing Album'
49      puts '3 Exit'
50      choice = read_integer_in_range("Please enter your choice:", 1, 3)
51      case choice
52      when 1
53        maintain_albums()
```

```
54      when 2
55        play_existing_album()
56      when 3
57        finished = true
58      else
59        puts 'Please select again'
60      end
61    end until finished
62  end
63
64  main()
```

```
PS D:\COS10009\CODE\LAB3> ruby 3_2P.rb
Main Menu:
1 To Enter or Update Album
2 To Play existing Album
3 Exit
Please enter your choice:
1
Maintain Albums Menu:
1 To Update Album Title
2 To Update Album Genre
3 To Enter Album
4 Exit
Please enter your choice:
1
You selected Update Album Title. Press enter to continue

Maintain Albums Menu:
1 To Update Album Title
2 To Update Album Genre
3 To Enter Album
4 Exit
Please enter your choice:
2
You selected Update Album Genre. Press enter to continue

Maintain Albums Menu:
1 To Update Album Title
2 To Update Album Genre
3 To Enter Album
4 Exit
Please enter your choice:
3
You selected Enter Album. Press enter to continue

Maintain Albums Menu:
1 To Update Album Title
2 To Update Album Genre
3 To Enter Album
4 Exit
Please enter your choice:
4
Main Menu:
1 To Enter or Update Album
2 To Play existing Album
3 Exit
```