



User Guide


1. Go to CMD Prompt (Press Win + R, type cmd, and hit Enter.):



2. Login to Server with SSH:
`#ssh user_name@10.16.1.50`




3. Press Enter & Enter your Password:



4. On the first time Login you can Change your Default PASSWORD.

Copy File to Server:

1. Go to CMD Prompt (Press Win + R, type cmd, and hit Enter.):



5. Navigate to the Folder where your file is located.

```
C:\WINDOWS\system32\cmd.exe

C:\Users\Administrator>cd Desktop
C:\Users\Administrator\Desktop>dir
Volume in drive C has no label.
Volume Serial Number is 9CDD-9A03

Directory of C:\Users\Administrator\Desktop

05/21/2025  02:54 PM    <DIR>          .
05/21/2025  02:54 PM    <DIR>          ..
05/21/2025  02:50 PM                5 script.py
               1 File(s)                5 bytes
               2 Dir(s)  245,540,741,120 bytes free

C:\Users\Administrator\Desktop>scp script.py tarun.verma@10.16.1.50:/home/tarun.verma
Password:
script.py                                           100%   5    0.3KB/s   00:00

C:\Users\Administrator\Desktop>
```

#scp file.txt <username>@10.16.1.50:/home/<username>

#scp -r folder <username>@10.16.1.50:/home/<username>

****this Command RUN in your Computer**

How to Run Code on Server:-

Sample Job Submission Script: -

One job submission script needs to be created as below: -

To Create a job script file:

```
[hpe@mgmt01~]$ nano submit.sh
```

```
#!/bin/bash
#PBS -N test
#PBS -q gpu
#PBS -l select=1:ncpus=10:ngpus=1:mem=10g
#PBS -j oe
#PBS -V
cd $PBS_O_WORKDIR
source /home/soft/anaconda3/etc/profile.d/conda.sh
conda init
conda activate
conda activate pytorch-gpu <replace pytorch-gpu with your own env_name>
module load cuda
python3 ./test.py <replace test.py with your python file_name>
```

To submit the Job :-

```
[hpe@mgmt01~]$ qsub submit.sh
```

To view the status of the Job :-

```
[hpe@mgmt01~]$ qstat -ans
```

To see detailed job information:

```
[hpe@mgmt01~]$ qstat -f <job_id>
```

Check the status of all job queues:

```
[hpe@mgmt01~]$ qstat -Q
```

To verify the status of the compute nodes:

```
[hpe@mgmt01~]$ pbsnodes -aSJ
```

Job Output and Error Files

Once the job completes, it will generate output and error files (typically in the same directory from where you submitted the job), as specified in your `my_pbs_job.sh` script:

Standard Output File:

This contains the standard output (stdout) of your job.

Error File:

This contains any errors (stderr) generated during execution.

Check Storage Quota:

```
[hpe@mgmt01~]$ myquota
```

```
[test @mgmt01 ~]$ myquota
Storage quota for user: test00
-----
Disk quotas for user test00 (uid 156900506):
    Filesystem kbytes  quota  limit  grace  files  quota  limit  grace
    /home    1036340*  8192   10240    -    11238    0     0     -
```

Create Own Python Virtual Environment

Step1: [hpe@mgmt01~]\$ source /home/soft/anaconda3/bin/activate [to activate]


Step2: [hpe@mgmt01~]\$ conda search python3 [search python versions]

Steps3: [hpe@mgmt01~]\$ conda create --name <env_name> python=3.10

Steps4: [hpe@mgmt01~]\$ conda activate <env_name>

Steps5: [hpe@mgmt01~]\$ (env_name) [test00@mgmt01 ~]\$ conda install jiwer

If package not available then goto <https://anaconda.org/> search here



The screenshot shows the Anaconda package page for 'jiwer'. It includes the following information:

- License: Apache-2.0
- Home: <https://github.com/jitsi/jiwer>
- 18260 total downloads
- Last upload: 15 days and 21 hours ago

Below this information is a section titled 'Installers' which shows a 'noarch' installer for version 'v3.0.5'. Underneath, it says 'conda install' followed by a help icon. Below that, it says 'To install this package run one of the following:' and provides the command 'conda install conda-forge::jiwer' in a code block.

Copy that command and execute on server :-

```
[hpe@mgmt01~]$ conda install conda-forge::jiwer
```

Jiwer will installed.

Change on PBS Script:

```
#!/bin/bash
#PBS -N test
#PBS -q gpu
#PBS -l select=1:ncpus=10:ngpus=1:mem=10g
#PBS -j oe
#PBS -V
cd $PBS_O_WORKDIR
source /home/soft/anaconda3/etc/profile.d/conda.sh
conda init
conda activate
conda activate pytorch-gpu <replace pytorch-gpu with your own env_name>
module load cuda
python3 ./test.py <replace test.py with your python file_name>
```