ZCL_CRM_BOR_PROXY Release 740 System CDA Class: ZCL CRM BOR PROXY Status: Active Attributes Description: BOR Proxy Instantiation: Abstract Not final Not released Fixed pt.arithmetic Program status: Customer Production Program Category: General Object Type Package: ZCRM Original lang.: EN Created by: P000520 Created on: 11.12.2014 Last changed by: P000520 Last changed on: 22.12.2014 Attributes Public attributes Description Ref. Type Attrib. Cat Init. value AV_TYPE Inst (read only) Object Type TYPE SWO_OBJTYP
AV_OBJID Inst (read only) Object key TYPE SWO TYPEID Protected attribute Attrib. Cat Description Ref. Type Init. value AV_OBJECT Inst Number of runtime object TYPE SWO OBJHND Methods Public methods CONSTRUCTOR Description: CONSTRUCTOR

Instance mthd

```
Importing parameter
         P_KEY TYPE SWO_TYPEID OPTIONAL (Object key)
         METHOD constructor.
           IF p key IS SUPPLIED.
            me->av objid = p key.
           ENDIF.
         ENDMETHOD.
       SET ATTRIBUTES
       Description: Sets control attributes of objects og this class.
       Instance mthd
       08.03.2015
                                      12:23:13
       ZCL CRM BOR PROXY Release 740
                                                      System
CDA
       Exceptions
         CX BAPI ERROR (BAPI Error Exception: Migrated Error Messages
Type "E")
         METHOD set attributes.
           DATA: lo_api TYPE REF TO lcl_api,
                 lx_error TYPE REF TO cx_bapi_error.
           lo api ?= me->get_api().
           TRY .
               lo api->get bor instance( EXPORTING
                                          p type = me->av type
                                           p key = me->av_objid
                                         RECEIVING
                                           r_object = me->av_object ).
             CATCH cx_bapi_error INTO lx_error.
               RAISE EXCEPTION lx_error.
           ENDTRY.
           FREE lo api.
         ENDMETHOD.
       GET PLAIN ATTRIBUTE
       Description: Returns the value of a plain attribute.
       Instance mthd
       Importing parameter
         P NAME TYPE SWO VERB (Object type component)
       Returning parameter
         VALUE (R VALUE) TYPE SWC VALUE (Character value)
```

Exceptions

```
CX BAPI ERROR (BAPI Error Exception: Migrated Error Messages
Type "E")
         METHOD get_plain_attribute.
           DATA: lo api TYPE REF TO lcl api,
                 lx error TYPE REF TO cx bapi error.
            IF me->av object IS INITIAL AND me->av objid IS NOT INITIAL.
                  me->set attributes().
                CATCH cx bapi error INTO lx error.
                 RAISE EXCEPTION lx error.
             ENDTRY.
            ENDIF.
            lo api ?= me->get api().
            TRY .
                lo_api->get_plain_attribute( EXPORTING
                                              p_object = me->av_object
                                              p name = p_name
                                             RECEIVING
                                              r value = r value ).
              CATCH cx bapi error INTO lx error.
                FREE lo api.
                RAISE EXCEPTION lx error.
            ENDTRY.
            FREE lo_api.
          ENDMETHOD.
        08.03.2015
                                        12:23:13
        ZCL_CRM_BOR_PROXY
                                      Release 740
                                                                System
CDA
        CALL METHOD PLAIN RESULT
        Description: Returns the result of a method that returns a plain
value.
        Instance mthd
        Importing parameter
         P NAME TYPE SWO VERB (Object type component)
        Returning parameter
         VALUE(R VALUE) TYPE SWC VALUE (Character value)
        Exceptions
         CX BAPI ERROR (BAPI Error Exception: Migrated Error Messages
Type "E")
```

```
METHOD call_method_plain_result.
            DATA: lo api TYPE REF TO lcl api,
                  lx error TYPE REF TO cx bapi error.
            IF me->av_object IS INITIAL AND me->av_objid IS NOT INITIAL.
              TRY .
                  me->set attributes().
                CATCH cx bapi error INTO lx error.
                  RAISE EXCEPTION lx error.
              ENDTRY.
            ENDIF.
            lo api ?= me->get api().
            TRY .
                lo api->call method plain result ( EXPORTING
                                                    p object = me-
>av object
                                                    p_name = p_name
                                                  RECEIVING
                                                    r value = r value ).
              CATCH cx bapi error INTO lx error.
                FREE lo api.
                RAISE EXCEPTION lx_error.
            ENDTRY.
            FREE lo api.
          ENDMETHOD.
        GET MULTILINE ATTRIBUTE
        Description: Returns the value of a table attribute.
        Instance mthd
        Importing parameter
          P NAME TYPE SWO VERB (Object type component)
        Returning parameter
          VALUE(RT VALUES) TYPE SWFTVALUE (Workflow: Table Type for XML
Character Stream)
        Exceptions
          CX BAPI ERROR (BAPI Error Exception: Migrated Error Messages
Type "E")
          METHOD get_multiline_attribute.
            DATA: lo api TYPE REF TO lcl api,
                  lx error TYPE REF TO cx bapi error.
            IF me->av object IS INITIAL AND me->av objid IS NOT INITIAL.
                  me->set attributes().
                CATCH cx_bapi_error INTO lx_error.
        08.03.2015
                                        12:23:13
3
        ZCL CRM BOR PROXY
                                      Release 740
                                                                 System
CDA
```

```
RAISE EXCEPTION lx error.
             ENDTRY.
            ENDIF.
            lo api ?= me->get api().
            TRY .
                lo api->get multiline attribute( EXPORTING
                                                   p object = me-
>av object
                                                  p_name = p_name
                                                 RECEIVING
                                                  rt values = rt values
) .
              CATCH cx_bapi_error INTO lx_error.
                FREE lo api.
                RAISE EXCEPTION lx error.
            ENDTRY.
            FREE lo api.
          ENDMETHOD.
        CMTD PARM NORESULT
        Description: Calls a method that requires parameters and returns
nothing.
        Instance mthd
        Importing parameter
          P NAME TYPE SWO VERB (Object type component)
          PT PARMS TYPE SWCONTTAB (Container Table)
        Exceptions
          CX BAPI ERROR (BAPI Error Exception: Migrated Error Messages
Type "E")
          METHOD cmtd parm noresult.
            DATA: lo api TYPE REF TO lcl api,
                  lx_error TYPE REF TO cx_bapi_error.
            IF me->av_object IS INITIAL AND me->av_objid IS NOT INITIAL.
             TRY .
                 me->set attributes().
                CATCH cx bapi error INTO lx error.
                 RAISE EXCEPTION lx error.
             ENDTRY.
            ENDIF.
            lo api ?= me->get api().
            TRY .
                lo api->cmtd parm noresult( EXPORTING
                                              p object = me->av object
                                              p name = p name
                                              pt parms = pt parms ).
              CATCH cx bapi error INTO lx error.
                FREE lo api.
                RAISE EXCEPTION lx error.
            ENDTRY.
            FREE lo api.
          ENDMETHOD.
        CALL STATIC METHOD
        Description: Calls a static method and returns a container table
        Instance mthd
```

```
08.03.2015
                                        12:23:13
4
        ZCL CRM BOR PROXY
                           Release 740
                                                                 System
CDA
        Importing parameter
         P NAME TYPE SWO VERB (Object type component)
         PT CONTAINER TYPE SWCONTTAB (Container Table)
        Returning parameter
         VALUE (RT CONTAINER) TYPE SWCONTTAB (Container Table)
        Exceptions
         CX BAPI ERROR (BAPI Error Exception: Migrated Error Messages
Type "E")
         METHOD call static method.
            DATA: lo api TYPE REF TO lcl api,
                  lx error TYPE REF TO cx bapi error.
            IF me->av object IS INITIAL AND me->av objid IS NOT INITIAL.
              TRY .
                  me->set attributes().
                CATCH cx bapi error INTO lx error.
                 RAISE EXCEPTION lx error.
             ENDTRY.
            ENDIF.
            lo_api ?= me->get_api().
            TRY .
                lo api->call static method( EXPORTING
                                              p_type = me->av_type
p_name = p_name
                                              pt parms = pt_container
                                             RECEIVING
                                              rt_results = rt_container
) .
              CATCH cx bapi error INTO lx error.
                FREE lo api.
                RAISE EXCEPTION lx error.
            ENDTRY.
            FREE lo api.
          ENDMETHOD.
        ADD ENTRY TO CONTAINER TABLE
        Description: Adds an entry to a container table.
        Instance mthd
        Importing parameter
          P ELEMENT TYPE ANY (Table name)
```

```
P FIELD TYPE ANY (Table field)
       CHANGING parameter
         CT_CONTAINER TYPE SWCONTTAB (Container Table)
       Exceptions
         CX BAPI ERROR (BAPI Error Exception: Migrated Error Messages
Type "E")
         METHOD add_entry_to_container_table.
           lt container TYPE swconttab.
           swc_set_element ct_container p_element p_field.
           IF sy-subrc <> 0.
             lw_return-type
                              = sy-msgty.
= sy-msgid.
             lw return-id
       08.03.2015
                                      12:23:13
5
       ZCL CRM BOR PROXY Release 740
                                                              System
CDA
             lw return-number = sy-msgno.
             lw_return-message_v1 = sy-msgv1.
             lw_return-message_v2 = sy-msgv2.
             lw_return-message_v3 = sy-msgv3.
             lw_return-message_v4 = sy-msgv4.
             APPEND lw return TO lt return.
             RAISE EXCEPTION TYPE cx bapi error
               EXPORTING
                 status = lt return.
           ENDIF.
         ENDMETHOD.
       FREE
       Description: Frees this object.
       Instance mthd
       Exceptions
         CX BAPI ERROR (BAPI Error Exception: Migrated Error Messages
Type "E")
         METHOD free.
           DATA: lo api TYPE REF TO lcl api,
                 lx error TYPE REF TO cx bapi error.
           IF me->av object IS INITIAL.
            RETURN.
           ENDIF.
           IF me->av object IS INITIAL AND me->av objid IS NOT INITIAL.
```

6

CDA

Importing parameter

Transfer Table)

Type "E")

Exceptions

```
TRY .
                 me->set_attributes().
               CATCH cx_bapi_error INTO lx_error.
                 RAISE EXCEPTION lx_error.
             ENDTRY.
           ENDIF.
           lo api ?= me->get api().
           TRY .
               lo api->free( me->av object ).
             CATCH cx_bapi_error INTO lx_error.
               FREE lo api.
               RAISE EXCEPTION lx error.
           ENDTRY.
           FREE lo_api.
         ENDMETHOD.
       COMMIT
       Description: Performs a commit.
        Instance mthd
         METHOD commit.
           DATA: lo api TYPE REF TO lcl api,
                 lx error TYPE REF TO cx bapi error.
           lo api ?= me->get_api().
           lo_api->commit().
           FREE lo api.
         ENDMETHOD.
       08.03.2015
                                       12:23:13
       ZCL CRM BOR PROXY
                             Release 740
                                                              System
       SET INSTANCE BY ID
       Description: Returns an instance of object related to the id
provided.
       Instance mthd
```

P ID TYPE RSOBJS NODE ID (Object Services: Node ID for

CX BAPI ERROR (BAPI Error Exception: Migrated Error Messages

```
GET OBJECT PLAIN ATTRIBUTE
        Description: Returns the value of a plain attribute of an obj.
attribute.
        Instance mthd
        Importing parameter
          P OBJECT TYPE SWO VERB (Object type component)
          P ATTRIB TYPE SWO VERB (Object type component)
        Returning parameter
          VALUE (R VALUE) TYPE SWC VALUE (Character value)
        Exceptions
          CX BAPI ERROR (BAPI Error Exception: Migrated Error Messages
Type "E")
          METHOD get_object_plain_attribute.
            DATA: lo_api TYPE REF TO lcl_api,
                  lx error TYPE REF TO cx bapi error.
            IF me->av_object IS INITIAL.
              TRY .
                  me->set attributes().
                CATCH cx bapi error INTO lx error.
                  RAISE EXCEPTION lx error.
              ENDTRY.
            ENDIF.
            lo api ?= get api().
            lo api->get object plain attribute(
              EXPORTING
                p handle = me->av object
                p_object = p_object
               p attrib = p_attrib
              RECEIVING
               r_value = r_value
                                               ) .
          ENDMETHOD.
        CALL METHOD WITH CONTAINER
        Description: Calls an instance method using container.
        Instance mthd
        Importing parameter
          P NAME TYPE SWO VERB (Object type component)
          PT CONTAINER TYPE SWCONTTAB (Container Table)
        Returning parameter
          VALUE(RT CONTAINER) TYPE SWCONTTAB (Container Table)
```

```
_____
```

08.03.2015 12:23:13

```
ZCL_CRM_BOR_PROXY Release 740 System CDA
```

```
Exceptions
          CX BAPI ERROR (BAPI Error Exception: Migrated Error Messages
Type "E")
          METHOD call method with container.
            DATA: lo api TYPE REF TO lcl api,
                  lx error TYPE REF TO cx bapi error.
            IF me->av object IS INITIAL AND me->av objid IS NOT INITIAL.
              TRY .
                  me->set attributes().
                CATCH cx bapi error INTO lx_error.
                  RAISE EXCEPTION lx_error.
              ENDTRY.
            ENDIF.
            lo api ?= me->get api().
            TRY .
                lo_api->call_method_with container(
                          EXPORTING
                            p object = me->av object
                            p_type = me->av_type
p_name = p_name
                            pt parms = pt container
                          RECEIVING
                            rt results = rt container ).
              CATCH cx bapi error INTO lx error.
                FREE lo_api.
                RAISE EXCEPTION lx error.
            ENDTRY.
            FREE lo_api.
          ENDMETHOD.
        Private methods
        GET API
        Description: Returns a API calls mediator.
        Instance mthd
        Returning parameter
          VALUE(RO API) TYPE REF TO OBJECT (API calls mediator
instance.)
          METHOD get_api.
            DATA lo_api TYPE REF TO lcl_api.
            lo api = NEW lcl api().
            IF lo api IS BOUND.
              ro_api = lo_api.
            ENDIF.
            FREE lo api.
          ENDMETHOD.
        Redefined Methods
        Local Types
        *"* use this source file for any type of declarations (class
```

"" definitions, interfaces or type declarations) you need for

```
*"* components in the private section
      08.03.2015
                                     12:23:13
       ZCL CRM BOR PROXY
                           Release 740
                                                            System
CDA
       Local class definitions
       "" use this source file for the definition and implementation of
       *"* local helper classes, interface definitions and type
       *"* declarations
       INCLUDE <cntn03>.
       * Class LCL API
        OVERVIEW: Objects of this class mediates API calls. It aims to
                   isolate this development from external dependencies,
as
                   might be desirable in tests.
                   The instances of this object is provided by the
private
                  method GET API of the main class
                   (ZCL CRM BOR PROXY). By redefining the
                  method GET API one can provide appropriated stubs,
which
                  must redefine the desired methods of LCL API,
instead of
                  accessing the real APIs.
       CLASS lcl api DEFINITION.
         PUBLIC SECTION.
          METHODS: get_bor_instance IMPORTING p_type TYPE
swo_objtyp
                                            p_key
                                                           TYPE
swo typeid
                                   RETURNING VALUE(r_object) TYPE
swo objhnd
                                  RAISING cx bapi error,
       * Method GET BOR INSTANCE
       *-----
____*
       * REQUIRES: The BOR type and key must be provided.
       * EFFECTS.: If the API SWO_CREATE returns an error, this method
```

```
returns exception type CX_BAPI_ERROR, otherwise
returns
                 the Number of runtime object.
       * -> P_TYPE Object Type.
* -> P_KEY Object key.
* <- R_OBJECT Number of runtime object.</pre>
            get plain attribute IMPORTING p object TYPE
swo objhnd
                                         p name TYPE swo verb
                                RETURNING VALUE(r value) TYPE swc value
                                RAISING cx_bapi_error,
       * Method GET PLAIN ATTRIBUTE
       *-----
       * REQUIRES: The Number of runtime object and the attribute name
must
                 be provided.
       * EFFECTS.: If the API SWO_INVOKE returns an error, this method
            returns exception type CX_BAPI_ERROR, otherwise
returns
            the value of the attribute.
       * -> P_OBJECT Number of runtime object.
* -> P_NAME Object type component (attribute name).
* <- R_VALUE Component value.</pre>
            call method plain result IMPORTING p object
                                                            TYPE
swo objhnd
     08.03.2015
                                12:23:13
      ZCL CRM BOR PROXY Release 740
                                                             System
CDA
                                               p name TYPE
swo verb
                                     RETURNING VALUE (r value) TYPE
swc value
                                     RAISING cx bapi error,
```

```
* Method CALL METHOD PLAIN RESULT
       * REQUIRES: The Number of runtime object and the method name must
           be provided.
       * EFFECTS.: If the API SWO INVOKE returns an error, this method
                  returns exception type CX BAPI ERROR, otherwise
returns
             the value returned by the method.
       * -> P_OBJECT Number of runtime object.
                         Object type component (method name). Component value.
       * -> P_NAME
* <- R_VALUE
            get multiline attribute IMPORTING p object
swo objhnd
                                             p_name
                                                             TYPE
swo verb
                                    RETURNING VALUE (rt values) TYPE
swftvalue
                                   RAISING cx_bapi_error,
       * Method GET MULTILINE ATTRIBUTE
       *----
       * REQUIRES: The Number of runtime object and the attribute name
must.
                 be provided.
       * EFFECTS.: If the API SWO_INVOKE returns an error, this method
                  returns exception type CX BAPI ERROR, otherwise
returns
                  a table holding the values of the multiline
attribute.
       * -> P_OBJECT Number of runtime object.

* -> P_NAME Object type component (method name).

* <- R_VALUE Component value.</pre>
             cmtd_parm_noresult IMPORTING p_object TYPE swo_objhnd
                                    p_name TYPE swo verb
                                        pt_parms TYPE swconttab
                              RAISING cx bapi_error,
       * Method CMTD PARM NORESULT
       *_____
       * REQUIRES: The Number of runtime object, the attribute name and
the
                 arguments list must be provided.
       * EFFECTS.: If the API SWO INVOKE returns an error, this method
                  returns exception type CX BAPI ERROR.
```

```
* -> P_OBJECT Number of runtime object.
* -> P_NAME Object type component (method name).
* -> PT_PARMS Container Table.
        *-----
____*
             call static method IMPORTING p type
                                                            TYPE
swo objtyp
                                           p name TYPE
swo verb
                                           pt parms TYPE
swconttab
                                 RETURNING VALUE(rt_results) TYPE
swconttab
                                 RAISING cx_bapi_error,
       08.03.2015
                                       12:23:13
10
      ZCL_CRM_BOR_PROXY Release 740 System
CDA
        * Method CALL_STATIC_METHOD
       ^{\star} EFFECTS.: If the API SWO INVOKE PERSISTENT returns an error
this
                  method returns exception type CX BAPI ERROR,
otherwise it
             returns the results of the processing.
       * -> P_TYPE Object Type.

* -> P_NAME Object type component (method name).

* -> PT_PARMS Container table holding the arguments.

* <- RT_RESULTS Container table holding the results.</pre>
        *----
             call_method_with_container IMPORTING p_object
                                                                    TYPE
swo objhnd
                                                                     TYPE
                                                   p_type
swo objtyp
                                                   p name
                                                                    TYPE
swo verb
                                                   pt_parms TYPE
swconttab
```

```
RETURNING VALUE (rt results) TYPE
swconttab
                                 RAISING cx_bapi_error,
      * Method CALL METHOD WITH CONTAINER
      *-----
      * EFFECTS.: If the API SWO INVOKE returns an error, this method
               returns exception type CX BAPI ERROR, otherwise it
               returns the results of the processing.
      *-----
      * -> P_OBJECT Number of runtime object.
* -> P_TYPE Object Type.

* -> P_NAME Object type component (method name).

* -> PT_PARMS Container table holding the arguments.

* <- RT_RESULTS Container table holding the results.</pre>
      *----
           CHANGING ct container TYPE swconttab
                        RAISING cx_bapi_error,
      * Method SWC ELEMENT SET
      *_____
      * REQUIRES: The element name and the name of the field to be
filled
                must be provided.
      * MODIFIES: If the API SWO INVOKE PERSISTENT returns an error
this
               method returns exception type CX BAPI ERROR,
otherwise it
               adds up an new line to the container table related to
the
               field provided.
      *-----
      * -> P_ELEMENT Element.
* -> P FIELD Field name.
      * <-> CT CONTAINER Container table.
           free IMPORTING p_object TYPE swo_objhnd
            RAISING cx bapi error,
      * Method FREE
      *-----
      08.03.2015
                                12:23:13
11
```

```
ZCL CRM BOR PROXY
                                  Release 740
                                                            System
CDA
       * REQUIRES: The object handler must be provided.
       * MODIFIES: If the API SWO FREE returns an error this method
returns
                  exception type CX_BAPI_ERROR, otherwise it frees the
                 related BOR.
       * -> P_ELEMENT Element.
* -> P_FIELD Field name.
* <-> CT_CONTAINER Container table.
            commit,
       * Method COMMIT
       *_____
       * MODIFIES: Commits database changes by calling API
       * BAPI_TRANSACTION_COMMIT.
       *-----
            get object plain attribute IMPORTING p handle
swo_objhnd
                                               p object
swo verb
                                               p_attrib
                                                            TYPE
swo verb
                                      RETURNING VALUE (r value) TYPE
swc value.
       *-----
       * Method GET OBJECT PLAIN ATTRIBUTE
       * REQUIRES: Current object handle, object attribute name and the
         name of the attribute must be provided.
       * EFFECTS.: Returns the result provided by API SWO INVOKE.
       * -> P_HANDLE Number of runtime object.
* -> P_OBJECT Object name.
* -> P_ATTRIB Attribute name.
* <- R_VALUE Attribute value.</pre>
____*
                                  "LCL_api DEFINITION
       CLASS 1cl api IMPLEMENTATION.
         METHOD get bor instance.
```

```
DATA: lw_swo_return TYPE swotreturn,
       lvc_dummy(1) TYPE c.
 CALL FUNCTION 'SWO CREATE'
   EXPORTING
    objtype
                   = p type
                   = p_key
    objkey
   IMPORTING
                  = r_object
    object
    return
                   = lw_swo_return
   EXCEPTIONS
    no_remote_objects = 1
     OTHERS = 2.
 IF lw swo return IS NOT INITIAL.
   m_raise_exception.
 ENDIF.
ENDMETHOD.
METHOD get plain attribute.
```

08.03.2015

12:23:13

12

ZCL_CRM_BOR_PROXY

Release 740

System

CDA

```
DATA: lt_container TYPE swconttab,
       lw_swo_return TYPE swotreturn,
       lvc dummy(1) TYPE c.
 FIELD-SYMBOLS < lw container > TYPE swcont.
  CALL FUNCTION 'SWO INVOKE'
    EXPORTING
     access = 'G'
object = p_object
verb = p_name
     verb
    IMPORTING
     return = lw_swo_return
   TABLES
     container = lt container.
  IF lw_swo_return IS NOT INITIAL.
   m raise exception.
 ELSE.
   LOOP AT lt container ASSIGNING < lw container >.
     r value = <lw_container>-value.
   ENDLOOP.
 ENDIF.
ENDMETHOD.
```

```
METHOD call_method_plain_result.
           DATA: lt_container TYPE swconttab,
                 lw_swo_return TYPE swotreturn,
                 lvc dummy(1) TYPE c.
           FIELD-SYMBOLS < lw container > TYPE swcont.
           CALL FUNCTION 'SWO INVOKE'
             EXPORTING
              access = 'C'
object = p_object
verb = p_name
             IMPORTING
              return = lw swo return
             TABLES
               container = lt container.
           IF lw_swo_return IS NOT INITIAL.
            m raise exception.
             LOOP AT 1t container ASSIGNING <1w container>.
               r value = <lw container>-value.
             ENDLOOP.
           ENDIF.
         ENDMETHOD.
         METHOD get_multiline_attribute.
           DATA: lt container TYPE swconttab,
                 lw_swo_return TYPE swotreturn,
                 lvc dummy(1) TYPE c.
           FIELD-SYMBOLS < lw container > TYPE swcont.
       08.03.2015
                                      12:23:13
13
       ZCL CRM BOR PROXY Release 740
                                                              System
CDA
           CALL FUNCTION 'SWO INVOKE'
             EXPORTING
              access = 'G'
object = p_object
worb = p_name
             IMPORTING
               return = lw_swo_return
             TABLES
               container = lt container.
           IF lw swo return IS NOT INITIAL.
```

m raise exception.

14

CDA

```
ELSE.
     LOOP AT lt_container ASSIGNING < lw_container >.
       APPEND < lw_container > - value TO rt_values.
     ENDLOOP.
   ENDIF.
  ENDMETHOD.
  METHOD cmtd parm noresult.
   DATA: lw_swo_return TYPE swotreturn,
         1vc dummy(1) TYPE c.
    CALL FUNCTION 'SWO INVOKE'
     EXPORTING
       access = 'C'
       object = p_object
verb = p_name
      IMPORTING
                = lw_swo_return
       return
     TABLES
       container = pt_parms.
    IF lw swo return IS NOT INITIAL.
     m raise exception.
   ENDIF.
  ENDMETHOD.
  METHOD call_static_method.
    DATA: lw oref static TYPE swotobjid,
          lw swo return TYPE swotreturn,
         lvc_dummy(1)     TYPE c,
lt_container     TYPE swconttab.
    lw_oref_static-objtype = p_type.
    lt_container = pt_parms.
    CALL FUNCTION 'SWO INVOKE PERSISTENT'
     EXPORTING
       object = lw_oref_static
verb = p_name
      IMPORTING
       return = lw_swo_return
       container = lt container.
    IF lw swo return IS NOT INITIAL.
     m raise exception.
08.03.2015
                               12:23:13
ZCL CRM BOR PROXY
                              Release 740
                                                        System
```

```
ENDIF.
 rt_results = lt_container.
ENDMETHOD.
METHOD call method with container.
 DATA: lw swo return TYPE swotreturn,
       lvc_dummy(1) TYPE c,
       lt container TYPE swconttab.
  lt_container = pt_parms.
  CALL FUNCTION 'SWO INVOKE'
   EXPORTING
     access = 'C'
     object = p_object

verb = p_name
   IMPORTING
              = lw swo_return
     return
   TABLES
     container = lt_container.
  IF lw swo return IS NOT INITIAL.
   m raise exception.
 ENDIF.
 rt_results = lt_container.
ENDMETHOD.
METHOD swc element set.
  DATA: lw return TYPE bapiret2,
       lt return TYPE bapiret2 t.
 CALL FUNCTION 'SWC ELEMENT SET'
   EXPORTING
                 = p_element
     element
     field
                 = p_field
   TABLES
                 = ct container
     container
   EXCEPTIONS
     type conflict = 1
     OTHERS
  IF sy-subrc <> 0.
   m regular_raise_exception.
 ENDIF.
ENDMETHOD.
METHOD free.
 TYPES: BEGIN OF ly object,
          handle TYPE swo_objhnd,
        END OF ly_object.
 DATA: lw_object TYPE ly_object,
       lw_return TYPE bapiret2,
       lt return TYPE bapiret2 t.
  lw object-handle = p object.
  swc_free_object lw_object.
  IF sy-subrc <> 0.
   m regular raise exception.
 ENDIF.
ENDMETHOD.
METHOD commit.
```

```
08.03.2015 12:23:13
15
```

ZCL_CRM_BOR_PROXY Release 740 System

CDA

```
CALL FUNCTION 'BAPI TRANSACTION COMMIT'
     EXPORTING
       wait = 'X'.
 ENDMETHOD.
 METHOD get object plain attribute.
   DATA: lw_mobject TYPE swc_object,
         lw aobject TYPE swc object.
   lw mobject-handle = p handle.
    swc get property: lw mobject p object lw aobject,
                     lw_aobject p_attrib r_value.
 ENDMETHOD.
ENDCLASS.
Macros
*"* use this source file for any macro definitions you need
*"* in the implementation part of the class
INCLUDE <cntn02>.
DEFINE m raise exception.
 message id lw_swo_return-workarea
    type 'E'
  number lw swo return-message
    with lw swo return-variable1 lw swo return-variable2
         lw swo return-variable3 lw swo return-variable4
    into lvc_dummy.
 lw_return-number = sy-msgno.
  lw return-message v1 = sy-msgv1.
 lw return-message v2 = sy-msgv2.
 lw return-message v3 = sy-msgv3.
 lw_return-message_v4 = sy-msgv4.
lw_return-message = lw_swo_return-text.
 append lw_return to lt_return.
 raise exception type cx_bapi_error
   exporting
     status = lt return.
END-OF-DEFINITION.
DEFINE m regular raise exception.
 lw return-number = sy-msgno.
 lw_return-message_v1 = sy-msgv1.
 lw return-message v2 = sy-msgv2.
 lw return-message v3 = sy-msgv3.
 lw return-message v4 = sy-msgv4.
 APPEND lw return TO lt return.
 RAISE EXCEPTION TYPE cx bapi error
```

6

EXPORTING
 status = lt_return.
END-OF-DEFINITION.

08.03.2015 12:23:13 16 Release 740 ZCL CRM BOR PROXY System CDA Overview Attributes 1 Attributes 1 Public attributes 1 Protected attribute Methods 1 Public methods CONSTRUCTOR 1 SET_ATTRIBUTES 1 GET_PLAIN_ATTRIBUTE 2 CALL_METHOD_PLAIN_RESULT 3 GET_MULTILINE_ATTRIBUTE 3 CMTD_PARM_NORESULT 4 CALL_STATIC_METHOD 4 ADD ENTRY TO CONTAINER TABLE FREE

_	COMMIT	
6	SET_INSTANCE_BY_ID	
7	GET_OBJECT_PLAIN_ATTRIBUTE	
7		
7	CALL_METHOD_WITH_CONTAINER	
8	Private methods	
8	GET_API	
	Redefined Methods	
8		
8	Local Types	
	Local class definitions	
9		
	Macros	16

08.03.2015

12:23:13

17