

Assignment Day – 4

1. **Connect a USB webcam to your computer, install any required drivers, and verify that the webcam works by opening the default camera app and capturing a photo.**



- a) **Connect the webcam :** Plug the USB webcam into an available USB port on the computer
- b) **Wait for detection :** Windows should automatically detect the webcam and install the required drivers.
- c) **Check the driver :** Open Device Manager -> Cameras and confirm that webcam is listed.
- d) **Open camera app :** Search for camera in the windows Start menu and open it.
- e) **Select the webcam :** if needed, select the connected USB webcam as the camera source.
- f) **Test the webcam :** check that the live video appears clearly on the screen.
- g) **Capture a photo :** click the camera/shutter button to take a photo
- h) **Verify the photo :** open the saved photo and confirm that the webcam captured the image successfully.

2. **Set up a local printer (USB or network), install the correct driver, and print a test page to confirm successful installation.**



Setting Up a Local Printer

- **Connect the printer:** Connect the printer to the computer using a USB cable or connect it to the same Wi-Fi network.
- **Turn on the printer:** Switch on the printer and make sure it is ready.
- **Install the driver:** Windows may install the driver automatically. If not, download and install the correct driver for the printer model.
- **Add the printer:** Go to Settings → Bluetooth & devices → Printers & scanners → Add device.
- **Select the printer:** Choose your connected printer from the list and complete the installation.
- **Print a test page:** Open the printer settings and select Print test page.
- **Verify:** If the test page prints correctly, the printer has been installed successfully.

3. **Simulate a connectivity issue by unplugging the printer's USB cable, then use Windows Device Manager to identify and resolve the 'printer not detected' problem.**

Hint: Check for error icons and use the 'Scan for hardware changes' option after reconnecting.



Resolve “Printer Not Detected” Problem

- **Unplug the USB cable:** Disconnect the printer’s USB cable from the computer.
- **Check the problem:** Open Settings → Bluetooth & devices → Printers & scanners and check that the printer is not detected.
- **Open Device Manager:** Press Windows + X → Device Manager.
- **Check for errors:** Look under Printers, Universal Serial Bus controllers, or Other devices for a yellow warning icon.
- **Reconnect the printer:** Plug the USB cable back into the computer and turn on the printer.
- **Scan for hardware changes:** In Device Manager, click Action → Scan for hardware changes.
- **Check the printer:** Confirm that the printer appears without an error icon.
- **Test printing:** Open Printers & scanners and print a test page to confirm that the problem is resolved.

4. A user reports that their webcam video is not displaying in Zoom, but it works in the default camera app. Troubleshoot and resolve the issue so the webcam works in both applications.

Hint: Check if another app is using the webcam or if Zoom permissions are enabled.



Troubleshoot Webcam Not Working in Zoom

- **Close other apps:** Close the Camera app or any other application that may be using the webcam.
- **Open Zoom:** Start Zoom and join a meeting or open the video settings.
- **Check camera selection:** Go to Zoom Settings → Video and select the correct USB webcam.
- **Check permissions:** Open Windows Settings → Privacy & security → Camera.
- **Enable camera access:** Turn on Camera access and Let apps access your camera.
- **Allow Zoom:** Make sure Zoom is allowed to access the camera.
- **Restart Zoom:** Close and reopen Zoom after changing the settings.
- **Test the webcam:** Start the video in Zoom and confirm that the webcam image is displayed correctly.