
DAY – 5 REVIEW AND PRACTICE PRACTICAL


Assignment - 21



Tops Technologies
Cyber Security


1. **Open Cisco Packet Tracer and create a new project file named 'HomeWiFiNetwork.pkt' with three PCs and one wireless router connected appropriately.**


➢



2. **Assign static IP addresses to each PC in your Packet Tracer network so they are on the same subnet (e.g., 192.168.10.x), and configure the default gateway to the router's IP.**


➢





3. **Test connectivity by using the Packet Tracer 'ping' tool to verify that all PCs can communicate with each other and the router.**
   Hint: Use the Command Prompt tool on each PC and type 'ping [other PC's IP]'.


➢




4. **Document each step you took to build and configure your Packet Tracer network, including screenshots of your topology and the IP configuration windows for each PC, in a Word or PDF file.**

➢

PC IP Configuration



Network Topology



Steps to Build and Configure the Network in Cisco Packet Tracer

Step 1: Add Network Devices

- **Open Cisco Packet Tracer.**
- **Add one WRT300N wireless router and three PCs (PC0, PC1, and PC2) to the workspace.**

Step 2: Connect the Devices

- **Use Copper Straight-Through cables to connect each PC's FastEthernet0 interface to a LAN Ethernet port on the router.**
- **Ensure that all connections show green indicators.**

Step 3: Configure the Router

- **Click the WRT300N router.**
- **Open the GUI or Config tab.**
- **Set the router's LAN IP address to 192.168.1.1 with subnet mask 255.255.255.0.**

Step 4: Configure PC0

- **Click PC0 and open Desktop → IP Configuration.**
- **Select Static and enter:**
    - **IPv4 Address: 192.168.1.2**
    - **Subnet Mask: 255.255.255.0**
    - **Default Gateway: 192.168.1.1**
    - **DNS Server: 0.0.0.0 (not configured)**

Step 5: Configure PC1

- **Open PC1 → Desktop → IP Configuration.**
- **Select Static and enter:**
    - **IPv4 Address: 192.168.1.3**
    - **Subnet Mask: 255.255.255.0**
    - **Default Gateway: 192.168.1.1**
    - **DNS Server: 0.0.0.0 (not configured)**

Step 6: Configure PC2

- **Open PC2 → Desktop → IP Configuration.**
- **Select Static and enter:**
    - **IPv4 Address: 192.168.1.4**
    - **Subnet Mask: 255.255.255.0**
    - **Default Gateway: 192.168.1.1**
    - **DNS Server: 0.0.0.0 (not configured)**

Step 7: Save the Project

- **Go to File → Save As.**
- **Save the project as Home_Network.pkt.**

Step 8: Test Network Connectivity

- **Click PC0 → Desktop → Command Prompt.**
- **Type ping 192.168.1.3 to test connectivity with PC1.**
- **Type ping 192.168.1.4 to test connectivity with PC2.**
- **Successful replies indicate that the PCs can communicate with each other.**