


Lab 12

VPC Peering Lab – 2 of 3


In Ohio region, we need to create VPC.



Click "Create VPC".




While creating VPC, type name tag as "Sansbound VPC Ohio" and IPV4 CIDR Block as 192.168.0.0/16 subnet.



Then click "Yes, create".



Then we need to create subnet for "Sansbound VPC Ohio" VPC.



Click "Create Subnet".




While creating Subnet, name tag as "Sansbound_Ohio_Public_Subnet", VPC as Sansbound_VPC_Ohio, Availability Zone – 2b (optional) and IPV4 CIDR block as "192.168.2.0/24" subnet.

Create Subnet				×	
Use the CIDR format to specify your subnet's IP address block (e.g., 10.0.0.0/24). Note that block sizes must be between a /16 netmask and /28 netmask. Also, note that a subnet can be the same size as your VPC. An IPv6 CIDR block must be a /64 CIDR block.					
Name tag	Sansbound_Ohio_Public		0		
VPC CIDRs	CIDR	Status	Status Reason		
	192.168.0.0/16	associated			
Availability Zone	us-east-2b 🔻 🐧				
IPv4 CIDR block	192.168.2.0/24		0		
				Cancel Yes, Create	

Then click "Yes, create".




We have required to create an internet gateway.



Click "Create Internet Gateway"



While creating Internet Gateway, name tag as "Sansbound_IGW_Ohio".




Click "Yes, create".



AWS Document Guide

Now internet gateway is in detached mode. We need to attach to Sansbound_VPC_Ohio VPC.




Attach to VPC		×				
Attach an Internet gateway to a VPC to enable communication with the Internet.						
VPC	vpc-805a92e8 Sansbound_VPC_Ohio ▼ 1					
	Canc	Yes, Attach				

Then click "Yes attach".






Type the route table value as sansbound_ohio_public








In Route table, route option click "Edit".






Click "Add another route"






Type default route 0.0.0.0/0 and select igw-* in target.



Then click "save".




In Subnet Associations, click "Edit" option.






In Subnet association edit option, select the check box of Sandbound_Ohio_Public_Subnet.



Then click "Save".




Now we need to create an instance in Ohio Region.






Select Microsoft Windows Server 2016 base





Select "t2.micro".



Click "Next".






In Network, select sansbound_vpc_ohio

Subnet, select sansbound ohio public subnet

Auto assign Public IP: Enable




Click "Next".




AWS Document Guide

Leave default settings and click "Next".






Type key as name and value as ohio public instance and click "Next".








Create a new security group and permit RDP port 3389.






AWS Document Guide

Click "Launch".





If you have already key pair select and launch the instance.



Click "Launch instances".