

Connecting and testing peripheral practical

- 1) Connect a USB webcam to your computer, install any required drivers, and verify that the webcam works by opening the default camera app and capturing a photo.

❖ Connect and Verify USB Webcam

Steps:

- Connect the USB webcam to an available USB port on the computer.
- Wait for Windows to detect the device automatically.
- If drivers are required:
 - Open Device Manager → Cameras/Imaging Devices.
 - Right-click the webcam → Update Driver.
 - Select Search automatically for drivers.
- Open the Camera app from the Windows Start menu.
- Check if the webcam video appears.
- Capture a photo to confirm the webcam is working properly.

- 2) Set up a local printer (USB or network), install the correct driver, and print a test page to confirm successful installation.

Install and Test a Local Printer

Steps:

- Connect the printer using:
 - USB cable, or
 - Network/Wi-Fi connection.
- Turn on the printer.
- Open Settings → Bluetooth & Devices → Printers & Scanners.
- Click Add Device and select the printer.
- Install the required printer driver.
- Open Control Panel → Devices and Printers.
- Right-click the printer → Printer Properties.

- Select Print Test Page.

- 3) Simulate a connectivity issue by unplugging the printer's USB cable, then use Windows Device Manager to identify and resolve the 'printer not detected' problem.

Hint: Check for error icons and use the 'Scan for hardware changes' option after reconnecting.

❖ **Problem Simulation:**

- Disconnect the printer USB cable from the computer.

❖ **Troubleshooting Steps:**

- Open Device Manager.
- Expand Printers or Universal Serial Bus Controllers.
- Look for:
 - Yellow warning icon
 - Missing printer device.
- Reconnect the printer USB cable.
- In Device Manager, click Action → Scan for hardware changes.
- Wait for Windows to detect the printer again.
- If the issue continues:
 - Restart the Print Spooler service.
 - Reinstall the printer driver.

- 4) A user reports that their webcam video is not displaying in Zoom, but it works in the default camera app. Troubleshoot and resolve the issue so the webcam works in both applications.

Hint: Check if another app is using the webcam or if Zoom permissions are enabled.

Troubleshooting Steps:

- Close the Windows Camera app and any other application using the webcam.
- Open Zoom.
- Go to:
 - Zoom Settings → Video.
- Check that the correct webcam is selected.

- Enable camera permission:
 - Settings → Privacy & Security → Camera
 - Turn on Camera access and allow Zoom.
- Restart Zoom.
- Update webcam drivers through Device Manager if needed.
- Test the video preview in Zoom.

Possible Causes:

- Another app is using the webcam.
- Zoom does not have camera permission.
- Wrong camera selected in Zoom.
- Outdated webcam driver.