
## Atlas Shell Configuration

## Configuring Atlas Shell

## Open Atlas Shell. Open Atlas Shell Settings

```
Atlas Shell 🛭
Initializing Shell, Please Wait...
                                                                                                                                                                                                                                     Atlas Shell Settings
import com.ensoftcorp.atlas.core.query.Q
import com.ensoftcorp.atlas.core.xcsg.XCSG
import com.ensoftcorp.atlas.core.db.graph.Graph
                                                                                                                                                                                                                                                      @
                                                                                                                                                                                                                                                     import com.ensoftcorp.atlas.core.db.graph.Node
import com.ensoftcorp.atlas.core.db.graph.Edge
import com.ensoftcorp.atlas.core.db.Accuracy.
import com.ensoftcorp.atlas.core.markup.IMarkup
                                                                                                                                                                                                                                                      æ
                                                                                                                                                                                                                                                     import com.ensoftcorp.atlas.core.markup.Markup
import com.ensoftcorp.atlas.core.markup.MarkupProperty
import java.awt.Color
import com.ensoftcorp.atlas.core.script.Common
                                                                                                                                                                                                                                                      8
                                                                                                                                                                                                                                                     85
import com.ensoftcorp.atlas.core.script.Common._
import com.ensoftcorp.atlas.core.script.CommonQueries
import com.ensoftcorp.atlas.core.script.CommonQueries._
                                                                                                                                                                                                                                                      Ð
import com.ensoftcorp.atlas.ui.shell.lib.ShellCommon._
Operation completed successfully...
```


You need to add com.ensoftcorp.open.commons and com.ensoftcorp.open.c.commons as Shell dependencies. Refer to the Screenshot below



Select the two indicated plugins and click Add to add them as dependencies. The final step is to edit Initialization Script. Switch to Initialization Script tab and add the following four lines to the script

```
import com.ensoftcorp.open.commons.analysis.CommonQueries
import com.ensoftcorp.open.commons.analysis.CommonQueries._
import com.ensoftcorp.open.c.commons.analysis.CommonQueries
import com.ensoftcorp.open.c.commons.analysis.CommonQueries.
```

Refer to the following screenshot in case of any confusion



Click Ok. If you see a message as shown below, then you have configured Atlas Shell correctly.

