在android SDK文档中有这样一个类,android.provider.Settings类提供android系统各个页面的跳转常量: 使用实例例:

startActivity(new Intent(Settings.ACTION_WIRELESS_SETTINGS)),即可跳到android手机网络设置页面。

如果要launch Mobile Networks Setting页面按如下方法:

Intent intent=new Intent(Settings.ACTION_DATA_ROAMING_SETTINGS);

ComponentName cName = new ComponentName("com.android.phone","com.android.phone.Settings"); intent.setComponent(cName);

startActivity(intent);

如果要进入Networks Operators页面按如下方法:

Intent intent = new Intent(Intent.ACTION_MAIN);

intent.setClassName("com.android.phone", "com.android.phone.NetworkSetting");

startActivity(intent);

如跳转到辅助功能模块设置界面

Intent intent = new Intent(Settings.ACTION_ACCESSIBILITY_SETTINGS);
startActivity(intent);

/*ACTION_ACCESSIBILITY_SETTINGS 辅助功能模块的显示设置。 */

String	ACTION_ACCESSIBILITY_SETTINGS 辅助功能模块的显示设置。	Activity Action: Show settings for accessibility modules.
String	ACTION_ADD_ACCOUNT 显示屏幕上创建一个新帐户添加帐户。	Activity Action: Show add account screen for creating a new account.
String	ACTION_AIRPLANE_MODE_SETTINGS 显示设置,以允许进入/退出飞行模式。	Activity Action: Show settings to allow entering/exiting airplane mode.
String	ACTION_APN_SETTINGS 显示设置,以允许配 置的APN。	Activity Action: Show settings to allow configuration of APNs.
String	ACTION_APPLICATION_DETAILS_SETTINGS 有关特定应用程序的详细信息的显示屏幕。	Activity Action: Show screen of details about a particular application.
String	ACTION_APPLICATION_DEVELOPMENT_SETTINGS 显示设置,以允许应用程序开发相关的设置配置	Activity Action: Show settings to allow configuration of application development-related settings.
String	ACTION_APPLICATION_SETTINGS 显示设置,以允许应用程序相关的设置配置	Activity Action: Show settings to allow configuration of application-related settings.
String	ACTION_BLUETOOTH_SETTINGS 显示设置,以允许蓝牙配置	Activity Action: Show settings to allow configuration of Bluetooth.
String	ACTION_DATA_ROAMING_SETTINGS 选择of2G/3G显示设置	Activity Action: Show settings for selection of 2G/3G.
String	ACTION_DATE_SETTINGS 显示日期和时间设置,以允许配置	Activity Action: Show settings to allow configuration of date and time.
String	ACTION_DEVICE_INFO_SETTINGS 显示一般的设备信息设置(序列号,软件版本,电话号码,等)	Activity Action: Show general device information settings (serial number, software version, phone number, etc.).
String	ACTION_DISPLAY_SETTINGS 显示设置,以允许配置显示	Activity Action: Show settings to allow configuration of display.
String	ACTION_INPUT_METHOD_SETTINGS 特别配置的输入方法,允许用户启用输入法的显示设置	Activity Action: Show settings to configure input methods, in particular allowing the user to enable input methods.
String	ACTION_INPUT_METHOD_SUBTYPE_SETTINGS 显示设置来启用/禁用输入法亚型	Activity Action: Show settings to enable/disable input method subtypes.

String	ACTION_INTERNAL_STORAGE_SETTINGS 内部存储的显示设置	Activity Action: Show settings for internal storage.
String	ACTION_LOCALE_SETTINGS 显示设置,以允许配置的语言环境	Activity Action: Show settings to allow configuration of locale.
String	ACTION_LOCATION_SOURCE_SETTINGS 显示设置,以允许当前位置源的配置	Activity Action: Show settings to allow configuration of current location sources.
String	ACTION_MANAGE_ALL_APPLICATIONS_SETTINGS 显示设置来管理所有的应用程序	Activity Action: Show settings to manage all applications.
String	ACTION_MANAGE_APPLICATIONS_SETTINGS 显示设置来管理安装的应用程序	Activity Action: Show settings to manage installed applications.
String	ACTION_MEMORY_CARD_SETTINGS 显示设置为存储卡存储	Activity Action: Show settings for memory card storage.
String	ACTION_NETWORK_OPERATOR_SETTINGS 选择网络运营商的显示设置	Activity Action: Show settings for selecting the network operator.
String	ACTION_PRIVACY_SETTINGS 显示设置,以允许配 置隐私选项	Activity Action: Show settings to allow configuration of privacy options.
String	ACTION_QUICK_LAUNCH_SETTINGS 显示设置,以允许快速启动快捷键的配置	Activity Action: Show settings to allow configuration of quick launch shortcuts.
String	ACTION_SEARCH_SETTINGS 全局搜索显示设置	Activity Action: Show settings for global search.
String	ACTION_SECURITY_SETTINGS 显示设置,以允许配置的安全性和位置隐私	Activity Action: Show settings to allow configuration of security and location privacy.
String	ACTION_SETTINGS 显示系统设置	Activity Action: Show system settings.
String	ACTION_SOUND_SETTINGS 显示设置,以允许配 置声音和音量	Activity Action: Show settings to allow configuration of sound and volume.
String	ACTION_SYNC_SETTINGS 显示设置,以允许配 置同步设置	Activity Action: Show settings to allow configuration of sync settings.
String	ACTION_USER_DICTIONARY_SETTINGS 显示设置来管理用户输入字典	Activity Action: Show settings to manage the user input dictionary.
String	ACTION_WIFI_IP_SETTINGS 显示设置,以允许配置一个静态IP地址的Wi – Fi	Activity Action: Show settings to allow configuration of a static IP address for Wi-Fi.
String	ACTION_WIFI_SETTINGS 显示设置,以允许 Wi – Fi 配置	Activity Action: Show settings to allow configuration of Wi-Fi.
String	ACTION_WIRELESS_SETTINGS 显示设置,以允许配置,如Wi – Fi,蓝牙和移动网络的无线 控制	Activity Action: Show settings to allow configuration of wireless controls such as Wi-Fi, Bluetooth and Mobile networks.
String	AUTHORITY	
String	EXTRA_AUTHORITIES 在推出活动的基础上给予的权力限制可选项。	Activity Extra: Limit available options in launched activity based on the given authority.
String	EXTRA_INPUT_METHOD_ID	