

HYPER LINK

In HTML, a hyperlink (or link) is created using the following tag:

```
<a>
```

The most critical part of a hyperlink is the `href` attribute, which specifies the destination URL or file path.

EXAMPLE:

```
<a href="https://example.com">  
Clickable Link Text  
</a>
```

- `target="_blank"`: This forces the browser to open the link in a new tab or window.
- `title="..."`: This creates a tooltip text that pops up when a user hovers their mouse cursor over the link.

Example:

```
<!DOCTYPE html>  
<html>  
<head>  
  <title>Basic Link</title>  
</head>  
<body>  
  
  <a href="https://google.com" target="_blank" title="Goes to Google">  
    Click to visit Google  
  </a>  
  
</body>  
</html>
```

ADDING IMAGES TO WEB PAGE

For adding an image in HTML we use this tag:

```

```

While adding images, they are often oversized and we have to adjust the length and width of the image by adding `height="value"` and `width="value"` to the above tag.

If you add only height to an `<img>` then width may be automatically adjusted depending on CSS and image aspect ratio.

Sometimes when we type the image path wrong, the image won't be visible — then we use `alt="your img details"` → it will tell what the image shows.

SYNTAX:

```

```

EXAMPLE:

```
<!DOCTYPE html>
<html>
<head>
  <title>Image Link Example</title>
</head>
<body>

  <h1>Clickable Image Example</h1>
  <p>Click the image below to visit Wikipedia:</p>

  <!-- The <a> tag creates the link, and the <img> tag sits inside it -->
  <a href="https://wikipedia.org" target="_blank">
    
  </a>

</body>
</html>
```

ADDING AUDIO TO A WEB PAGE IN HTML

To insert audio in HTML, use the following opening tag:

```
<audio>
```

Unlike the image tag, the audio tag is a container element that requires a closing tag:

```
</audio>
```

Audio is added between the opening and closing tags.

```
<audio controls>  
  <source src="your address of audio (mp3)">  
</audio>
```

`controls` must be added — without this, audio cannot be played in a normal user interface.

- `autoplay`: Instructs the browser to start playing the track as soon as the page loads.
- `muted`: Starts the audio volume at zero. This allows the browser to bypass strict privacy rules and actually let the autoplay function work. The user can unmute it manually if they want to.
- `loop`: Ensures that when the song ends, it automatically restarts from the beginning without stopping.