









AWS CLOUD COMPUTING

LAUNCHING AN AMAZON LINUX ELASTIC COMPUTE CLOUD (EC2)
INSTANCE







Launching an Amazon Linux Elastic Compute Cloud (EC2) **Instance**



4 de cos

Andhra Pradesh State Skill Development Corporation (APSSDC)




Launching Amazon Linux EC2 Instance

Amazon EC2: Amazon Elastic Compute Cloud (Amazon EC2) is a web service that provides secure, resizable compute capacity in the cloud. It is designed to make web-scale computing easier for developers. It is a simple web service interface that allows you to obtain and configure capacity with minimal friction. It provides you with complete control of your computing resources and lets you run on Amazon's proven computing environment. AmazonEC2 reduces the time required to obtain and boot new server instances (called Amazon EC2 instances) to minutes, allowing you to quickly scale capacity, both up and down, as your computing requirements change.

Objective:

To Launch Amazon Linux instances and to connect from Linux and Windows client PC.



<u>Setting Up with Amazon EC2</u>: Sign Up for AWS: When you sign up for Amazon Web Services (AWS), your AWS account is automatically signed up for all services in AWS, including Amazon EC2.

In the navigation pane first of all you need to choose your region and then click on EC2 in the Compute services.

Launching Amazon Linux EC2 Instance

Step 1: Choose an Amazon Machine Image (AMI)


An AMI is a template that contains the software configuration (operating system, application server, and applications) required to launch your instance. You can select an AMI provided by AWS, our user community, or the AWS Marketplace; or you can select one of your own AMIs.









Select Amazon Linux AMI 2018.03.0(HVM), SSD Volume Type ami0761dd91277e34178



Step 2: Choose an Instance Type Amazon

EC2 provides a wide selection of instance types optimized to fit different use cases. Instances are virtual servers that can run applications. They have varying combinations of CPU, memory, storage, and networking capacity, and give you the flexibility to choose the appropriate mix of resources for your applications.












Step 3: Configure Instance Details

Configure the instance to suit your requirements. You can launch multiple instances from the same AMI, request Spot instances to take advantage of the lower pricing, assign an access management role to the instance, and more.




Select Based on your requirement select instance type and subnet.

Step 4: Add Storage

Your instance will be launched with the following storage device settings. You can attach additional EBS volumes and instance store volumes to your instance, or edit the settings of the root volume. You can also attach additional EBS volumes after launching an instance, but not instance store volumes






Step 5: Add Tags

Feedback English (US)

A tag consists of a case-sensitive key-value pair. For example, you could define a tag with key = Name and value = Webserver.

Cancel Previous Review and Launch

Next: Add Tags




Step 6: Configure Security Group

A security group is a set of firewall rules that control the traffic for your instance. On this page, you can add rules to allow specific traffic to reach your instance. For example, if you want to set up a web server and allow Internet traffic to reach your instance, add rules that allow unrestricted access to the HTTP and HTTPS ports. You can create a new security group or select from an existing one .









Click on → Review and launch

Step 7: Review Instance Launch

Please review your instance launch details. You can go back to edit changes for each section. Click **Launch** to assign a key pair to your instance and complete the launch process.


Create a Key Pair:

Before launching your instance AWS uses public-key cryptography to secure the login information for your instance. A Linux instance has no password; you use a key pair to log in to your instance securely. You specify the name of the key pair when you launch your instance, then provide the private key when you login using SSH. If you haven't created a key pair already, you can create one using the Amazon EC2 console. From the navigation bar, select a region for the key pair. You can select any region that's available to you, regardless of your location. However, key pairs are specific to a region; for example, if you plan to launch an instance in the US East (Ohio) Region, you must create a key pair for the instance in the US East (Ohio) Region.









To connect to your instance using your key pair, To connect to your Linux instance from a computer running Mac or Linux, you'll specify the .pem file to your SSH client with the -i option and the path to your private key.

To connect to Amazon Linux instance from linux client operating system

Command:

\$ ssh -i "linux1.pem" ec2-user@ec2-54-152-135-243.compute-1.amazonaws.com

Select your instance and make sure your key (pem file) matches your key pair name



To connect to Amazon Linux instance from Windows client operating system






To connect to your Amazon Linux instance from a computer running Windows, you can use either MindTerm or PuTTY. If you plan to use PuTTY, you'll need to install it and use the following procedure to convert the .pem file to a .ppk file(for generation of PPK file Install Puttygen)

Skill AP

Download PuTTY: https://www.chiark.greenend.org.uk/~sgtatham/putty/latest.html.

To prepare to connect to a Linux instance from Windows using PuTTY, CONVERT YOUR PEM FILE TO PPK FORMAT

1. Open puttygen and load the pem file into the puttygen




2. Save the private key by assigning a name to that file










- → Open Putty
- i. Enter Host Name
- ii.Select your PPK file.
- iii.Open your terminal Session



Installing a NGINX Web Server on Amazon

To install and start the NGINX web server on Amazon Linux.

1. Connect to your instance in putty

User name: ec2-user









- 2. To ensure that all of your software packages are up to date, perform a quick software update on your instance. **\$ yum update -y**
- 3. Now that your instance is current, you can install the Nginx web server \$ yum install nginx -y
- 4. Restart the Apache web server. \$ service nginx restart
- 5. Also start all the web servers by executing its commands
- 6. If your server is installed and running, and your file permissions are set correctly, your ec2-user account should be able to create a file in the /usr/share/nginx/html directory that is available from the internet
- 7. In the web browser, type the URL of the file that you just created. This URL is the public DNS or IP address of your instance followed by a forward slash and the file name.

e.g: 54.152.135.243





NGINX NGINX